



BB FlashBack v(

User Manual and How-To Guide

I. Quick Start Guide	1
Recording a movie	2
How to make your first recording	2
Editing your movie	6
The toolbar	6
Editing frames	9
How to delete frames:	9
How to insert frames:	9
How to crop a movie:	9
Annotating your movie	10
How to add text to a movie	10
How to add an image to a movie	15
Using zoom/pan, cropping and autoscroll	17
How to zoom or pan:	17
How to crop a movie and use the autoscroll	18
Publishing your movie	20
Exporting your movie	20
Uploading to YouTube for easy sharing	22
II. How-To Guides	27
Working with Frames	28
How to delete frames:	28
How to insert frames:	28
Tracks and Clips	29
How to select a clip:	29
How to select multiple clips:	29
How to select a section of a clip:	29
How to move a clip:	29
How to select or de-select a track:	29
How to select multiple tracks:	30
Changing Volume and Muting	31
How to mute a track:	31
How to change the volume of a track:	31
How to mute a section of sound:	31
How to change the volume of a clip:	31
Deleting Sound	33
How to delete a whole clip:	33
How to delete a section of a clip:	33
How to delete sound and frames at the same time:	33
How to delete a track:	34
Inserting Silence	35
How to add silence to a clip:	35
How to insert silence and frames together:	36
Editing Sound and Video Together	39
How to edit sound without affecting video:	39
How to edit sound and affect the video:	39
Removing Background Noise	41
How to remove noise from a clip:	41
Fading a Clip In and Out	42
How to fade a clip in and out:	42
Adding Sound	43
How to add an existing sound file:	43
How to record a sound clip:	43
Adding Text and Images, Highlights, Arrows and Buttons	44
How to add text to a movie:	44

How to add an image to a movie:	46
How to add a highlight to your movie:	47
How to insert an arrow:	48
How to add a button:	50
Tips for better performance recording	53
How to change the recorder settings:	53
Saving your recordings as Flash	55
How to export as Flash:	55
Creating Pan and Zoom Effects	57
How to zoom in:	57
How to pan, while zoomed in:	59
How to zoom out from a previous zoom in:	60
Using Autoscroll	62
How to add a cropping rectangle:	62
How to remove a cropping rectangle:	62
How to add an autoscroll:	62
How to remove an autoscroll:	62
Recording from the Webcam	63
How to record the webcam whilst you record the screen:	63
How to record the webcam only:	64
How to insert a WebCam recording:	66
How to edit the WebCam recording:	67
How to move or resize the WebCam recording:	67
Adding Watermarks	68
How to add a watermark:	68
Inserting A Video File	69
How to insert video:	69
Scheduled Recording	70
How to schedule a recording:	70
Cursor Highlighting	72
How to highlight the cursor:	72
III. User Guide	73
Professional Edition v4	74
Contacting Blueberry	75
System Requirements	76
Software Requirements	76
Hardware Requirements	76
Buying BB Flashback	77
Buying a licence	77
Problems with licence keys	77
Resellers	78
Getting Started	79
BB FlashBack Basics	79
The Recorder	79
The Player	79
To get started	80
Recording movies	81
To view the movie	81
Playing back movies	81
From The Welcome Window	81
Playing a movie from Recorder	82
Sharing movies	82
Sharing Movies	83
Using BB FlashBack	85

Recorder Windows	85
The Recorder Main Window	85
The Recorder main menu	86
The movie file sub-menu	88
The Recorder Options window	90
Adding a Marker while recording	91
Using Recorder when it is minimized	91
Recorder features	93
About Recorder features	93
Recording windows and regions	94
Recording multi monitor systems	95
Windows display options	95
Capturing keystrokes	97
Limiting the movie file size	98
Defining and using hotkeys	99
Customising delays	99
Recording Webcam Video	99
Record modes and performance	101
Troubleshooting video recording	102
Recording sound	104
Troubleshooting sound recording	105
Scheduled recording	108
Record-time Notes	108
The Player	110
The Player window	110
The Timeline and Frame bar	112
Webcam / Picture-in-Picture Video	113
The Player Toolbars	115
The Player Main Menu	117
Viewing key presses	127
Other Player Features	130
Converting AVI files to FlashBack movies	130
Command-line options	131
Editing Movies	132
About editing movies	132
Working with frames	132
Annotating movies	137
Zoom-Pan Effects	147
Cropping and Autoscrolling	150
The Mouse Cursor	151
Removing inactive sections	154
Using Markers in movies	154
Inserting video files	155
Pauses	155
Start and End Titles	156
Displaying invisible keystrokes	157
Transitions	157
Exporting Movies	159
File Formats	159
Comparison of Export formats	161
Exporting to Flash Format	162
Exporting to Quicktime (H264)	173
Exporting to Windows Media Video (WMV)	175
Exporting to AVI format	177

About AVI codecs	177
Exporting to MPEG4	179
Exporting to Standalone EXE	180
Exporting to MS PowerPoint	181
Exporting to GIF	181
Sound export options	181
Batch Exports	182
Uploading Movies	183
How to Upload a Movie	183
Uploading to FTP and FileCopy	184
Creating upload profiles	185
Working with Sound	186
Adding and Recording Sound into a Movie	186
The Sound Options Window	187
Sound Synchronisation Problems	188
Changing the Volume of a Track or Clip	188
Removing Noise	189
Fading Sounds In or Out	189
Volume Level Processing	189
Editing Sound	190
Merging and Splitting Clips and Tracks	192
Sound Editing Operations	193
More About Selecting Sound and Frames	194
Using BB FlashBack from the Command Line	196
Support	198
Contacting Support	198
Troubleshooting FAQ	198
When I installed and when I run Recorder, I see a warning about ASUS software	198
My system runs extremely slowly when recording	198
When recording I see an error message referring to the BB Capture Driver	198
I'm trying to record a DVD or video clip, but it fails or the results are poor	198
What affects the file size of my final movie file?	198
When I replay my movie graphics or text are not displayed correctly or missing altogether	199
I cannot hear any sound when replaying my movie	199
My licence key is not accepted by the program	199
My FBR movie file will not open in the Player	199
I've exported my movie to an AVI file. This plays fine on my PC but not in other computers	200
When I export to any format, I get a 'created by' image in the top right corner. Will this appear when I buy a licence?	200
I've exported my movie to Flash but the SWF file appears distorted or low quality	200
I record with sound, but when I play back the movie, the sound and video become more and more out of sync	200
Reporting Problems	201
How to report a problem to Blueberry	201
Checking for Updates to BB FlashBack	201
How to check for updates to BB FlashBack	201
Automatic check for updates	202

Part I. Quick Start Guide

Recording a movie

First you need to make a recording which you can edit and publish.


How to make your first recording

Here, you will use BB FlashBack Recorder to record a movie which you can then edit in BB FlashBack Player

1. Open the BB FlashBack Pro 3 Recorder from the windows start menu.
2. On the welcome screen, click **Record a new movie**;




3. Set the recording options and click the record button;



Recording a movie

4. In the options, the **Record: Region** was selected, so set the size and position of the region and click **Record**;



5. Click the stop button to end recording;




6. Click **Save** and follow the steps to save the recording;



Editing your movie

First, open BB FlashBack Pro 3 Player and then open the movie you have recorded;




The toolbar

Use the toolbar to edit the movie. An overview of the whole toolbar is shown below.














The toolbar buttons are grouped into sections according to their function. The top left of the toolbar gives quick access to saving and publishing options.








The middle of the top row of buttons provides shortcuts to objects that you can insert into a movie.



- Click  **Properties** to edit the properties of any object which has been inserted into the movie
- Click  to delete any object from the movie
- Click  to insert a textbox
- Click  to insert an image
- Click  to highlight a section of your screen
- Click  to add a button
- Click  to insert an arrow
- Click  to insert another movie
- Click  to set a marker
- Click  to insert a watermark
- Click  to pause a section of the movie

The top right of the toolbar gives quick access to effects




- Click  to add a highlight to the mouse cursor
- Click  **Add Zoom/Pan** to insert or edit a zoom or pan
- Click  to delete an existing zoom or pan
- Click  to set a cropping rectangle
- Click  to add start and end titles to the movie
- Click **Apply Effects** to switch the effects on whilst you edit the movie

The middle left part of the toolbar gives you the option to play a short section of the movie, or jump to a different part








The middle right part of the toolbar allows you to change the viewing options
















The bottom left of the toolbar gives quick access to basic editing options



- Click   to undo or redo previous steps.
- Click  to delete
- Click  to crop the movie to a selected area
- Click  to insert

The bottom right of the toolbar is for sound editing operations



- Click  to add a new sound track.
- Click  to add a new sound.
- Click  to record a new sound.
- Click   to adjust the volume levels or mute a track or clip.
- Click  to apply a fade in or fade out to a clip.
- Click  to split a sound clip.
- Click  to merge sound clips.
- Click  to merge sound tracks.
- Click  to copy sound.
- Click  to cut sound.
- Click  to paste a copied or cut sound.
- Click  adjust or mute the master volume.


The playback bar gives easy access to playing the movie at various speeds, skipping forward and back or going directly to a different part of the movie.



Editing frames

The framebar gives easy access to edit any individual frame or groups of frames in the movie

You can insert and delete frames, and you can crop a movie down to specific frames



How to delete frames:

1. Select the first or last frame to be deleted
2. Drag the mouse across the frame bar to select additional frames
3. Press the delete key on the keyboard.

Or


Click  on the toolbar.

Or

Click **Edit -> Delete Frame(s)...** in the menu.

4. Click **OK**

How to insert frames:


1. Select the point where you wish to insert the frames
2. Click  on the toolbar.

Or

Click **Edit -> Insert Frame(s)...** in the menu.

3. Enter the number of frames you wish to insert
4. Click **OK**.


How to crop a movie:

1. Select the frame where you want to movie to begin.
2. Click and drag across the framebar until you reach the frame where you want the movie to end
3. Click  on the toolbar.

Or

Click **Edit -> Crop Frame(s)...** in the menu.


4. Click **OK** to confirm the edit;



Annotating your movie

You can add text, images and other objects to a movie.


How to add text to a movie

1. Select the frame where you want to insert the textbox.
2. Click  on the toolbar.


Or

Click **Insert -> Text** in the menu.


3. Set the properties of the textbox;




4. Set the appearance of the textbox;




5. You can create and edit styles to use with textboxes throughout a movie;



6. When you are creating a textbox, you can set the size and position. Alternatively, once the textbox has been created, you can click and drag in the view screen to manually resize and move it;




7. You can create a transition to fade the textbox in and out;



8. Click **OK** to insert the textbox.


How to add an image to a movie

1. Select the frame where you want to insert the image.
2. Click  on the toolbar.

Or


Click **Insert** -> **Image** in the menu.

3. Click **Load Image**;



4. Browse to the image, select it and click **Open**.

5. Set the properties of your image.



- Set the size and position of where it will appear in the movie from the **Position** tab.
- Add a fade in or fade out, using the **Transitions** tab;


6. Click **OK** to insert the image.

You can also insert highlights, buttons, arrows and other objects into the movie in a similar way.

Using zoom/pan, cropping and autoscroll

You can create zoom and pan effects in a movie. You can also crop a large movie to a smaller section and use the autoscroll effect to follow the mouse, missing none of the action.


How to zoom or pan:

1. Select the frame where you want to add the zoom or pan.
2. Click  Add Zoom/Pan on the toolbar.

Or

Click **Effects -> Add ZoomPan** in the menu.

3. Set the properties of the zoom;
 - Select **Custom Area** to zoom to a particular region of the movie.
 - Select **Whole Movie** to zoom back to show the entire movie if you previously added a zoom-in.
 - The transition speed sets how quickly the zoom or pan will appear on screen.




4. Click **OK** to insert the zoom effect.

Click and drag to re-size the zoom/pan.

Please note, the zoom will remain in the movie until the end, or another zoom effect is created.

How to crop a movie and use the autoscroll

1. First, add a cropping rectangle to the movie:

Click  on the toolbar.

Or

Click **Effects** -> **Set Cropping Rectangle** in the menu.

2. Then add the autoscroll effect:

Click **Effects**.

3. Go to the **Autoscroll Cropping Rectangle** submenu.

4. Click **Mouse In Centre**.

Or

Click **Mouse Near Centre**.

The cropping rectangle can be resized in the view screen. When you export the movie, only the area within the cropping rectangle will be exported.

The cropping rectangle will follow the mouse cursor as it moves across the screen when the autoscroll is set.


If zoom and pan effects are being used, a zoom in or pan will only show sections within the cropping rectangle.

Publishing your movie

When you have finished editing the movie, it can be exported in a variety of formats and can be uploaded to YouTube.


Exporting your movie

Here I will demonstrate how to export the movie to Flash

1. Click  **Export** on the toolbar.

Or


Click **File** -> **Export** in the menu.



2. Select the Flash export format;

3. Click **OK**.

4. Set the Flash Export Options



5. Click **Export**.


6. Choose where to save the exported files and click **Save**.

Three files are exported and you can choose view the export once completed

To view the movie in a web browser, ensure that you open the .html file that has been exported.

Please note, each export format comes with different options to include in the export.

1. When exporting to AVI, you need to select the Codec;




2. After selecting the Codec, you can set the AVI export options;

For example, you may choose to export the movie to AVI (which can be opened and edited again in FlashBack);

Uploading to YouTube for easy sharing


You can upload a movie to YouTube, directly from BB Flashback Pro 3 Player

1. Click  Upload to YouTube ▼ on the toolbar.

Or


Click **File** -> **Upload** -> **YouTube** in the menu.

2. Type in your username and password and click **OK**;



The screenshot shows a dialog box titled "Upload Movie" with a close button (X) in the top right corner. Inside the dialog, the text "Uploading to YouTube" is displayed. Below this, there is a "Login" section with a horizontal line. The instruction "Enter your YouTube name and password." is followed by two input fields. The "Name:" field contains the text "xxx@xxx.xxx". The "Password:" field is filled with ten black dots. At the bottom of the dialog, there are three buttons: "OK", "Cancel", and "Help". A mouse cursor is pointing at the "OK" button, which has a yellow starburst effect around it.

3. Complete the movie details and click **OK**;




The screenshot shows a dialog box titled 'Test6' with a close button (X) in the top right corner. The main heading inside the dialog is 'Uploading to YouTube'. Below this, there is a section titled 'Movie Details' with a horizontal line underneath. The 'Movie Details' section contains the following fields:

- Title:** A text input field containing '3B FlashBack Example'.
- Description:** A text input field containing 'Example'.
- Category:** A dropdown menu with 'Science & Technology' selected.
- Tags:** A text input field containing 'tag1,tag2'. Below this field is the text '(separate with ,)'.
- Private:** A checkbox that is checked, indicated by a blue checkmark.


At the bottom of the dialog, there are three buttons: 'OK', 'Cancel', and 'Help'. A mouse cursor is pointing at the 'OK' button, which is highlighted with a yellow starburst effect.

4. Set the movie size and click **OK**;




Note: FlashBack will show sizes equal to and lower than the size of the movie i.e. it won't show the 1080p option if the movie you're uploading is only 400 pixels high.

5. You will receive a message to confirm if the upload was successful;



6. Click **Open in Browser** to view the movie in YouTube;



Part II. How-To Guides

Working with Frames

You can add and delete frames from a section of your movie. This allows you to add new sections to your movie or remove any sections you no longer need.




See Video

How to delete frames:

1. Select the first or last frame to be deleted.
2. Drag the mouse across the frame bar to select additional frames.
3. Press the delete key on the keyboard.

Or


Click  on the toolbar.

Or

Click **Edit -> Delete Frame(s)...** in the menu.

4. Click **OK**.

How to insert frames:

1. Select the point where you wish to insert the frames.
2. Click  on the toolbar.

Or

Click **Edit -> Insert Frame(s)...** in the menu.

3. Enter the number of frames you wish to insert.
4. Click **OK**.

Tracks and Clips

A clip is a piece of sound which can be edited and moved independently of any other clip. A track is series of one or more clips and can be edited to change every clip it contains.



See Video

How to select a clip:

1. Click the handle of the clip;



How to select multiple clips:

1. Click the handle of the clip;



2. Hold the shift key on the keyboard
3. Click the handle above each additional track.

How to select a section of a clip:

1. Click and drag to highlight the section;




How to move a clip:

1. Click and drag the handle to the left or right;



How to select or de-select a track:

1. Click on the track header;



A pink highlight indicates it is selected.

How to select multiple tracks:

1. Click on each individual track header;



A pink highlight indicates which tracks are selected.

Changing Volume and Muting

You can change the volume of a track, or mute it. You can also change the volume of a clip and mute it.



See Video

How to mute a track:

1. Select the track you want to change.
2. Right-click on the track header;



3. Click **Mute Track**.

How to change the volume of a track:

1. Select the track you want to change.
2. Right-click on the track header ;




3. Click **Volume Up** or **Volume Down**

How to mute a section of sound:

1. Select the track you want to change.
2. Click and drag to highlight the section you want to mute;



3. Click  on the toolbar.

Or

Click **Sound -> Mute Sound Selection** in the menu

How to change the volume of a clip:

1. Select the track you want to change.

2. Click and drag to highlight the section you want to mute;



3. Click on the toolbar.

Or

Click **Sound -> Increase Sound Volume** or **Decrease Sound Volume** in the menu.

Deleting Sound

You can delete an entire track or clip or part of a clip from a movie.



See Video

How to delete a whole clip:

1. Select the track you want to change.
2. Click on the handle of the clip.



3. Right-click on the clip.
4. Click **Delete Clip**.
5. Click **Yes**.

How to delete a section of a clip:

1. Select the track you want to change.
2. Click and drag to highlight the section you want to delete;




3. Right-click on the selection.
4. Click **Delete Selection**.
5. Choose to shift the remaining sound to the left or leave it where it is and click **OK**.

How to delete sound and frames at the same time:

1. Select the track you want to change.
2. Click and drag to highlight the section you want to delete;
3. Press the delete key on the keyboard.

Or

Click  on the toolbar.

Or

Click **Edit -> Delete Frame(s)...** in the menu.

4. Select which tracks you want to edit and click **OK**.
5. Choose to shift the remaining sound to the left or leave it where it is and click **OK**.

How to delete a track:

1. Select the track you want to delete.
2. Right-click on the track header.



3. Click **Delete**.
4. Click **Yes**.

Inserting Silence


You can insert silence into a clip with or without inserting additional frames.




See Video

How to add silence to a clip:

1. Select the track you want to change.
2. Click on the point where you want to insert silence.
3. Right-click and select **Insert Silence**.
4. Choose how much silence you want to insert;




5. Choose how to shift the sound to the right;



6. Click **OK**.


How to insert silence and frames together:

1. Select the track you want to change.
2. Select the framebar header.
3. Click on the point where you want to insert silence.
4. Click  on the toolbar.

Or


Click **Edit -> Insert Frame(s)...** in the menu.

5. Tick any additional tracks you want to edit;




6. Click **OK**.

7. Choose how much silence you want to insert;



8. Choose how to shift the sound to the right;



9. Click **OK**.

Editing Sound and Video Together

A sound clip can be edited without the edit affecting the video frames. A sound clip can also be edited with the same edit applying to the video frames.



See Video

How to edit sound without affecting video:

1. Ensure the sound track(s) you want to edit are selected and the Frame header is not;



2. Proceed with the edit.


How to edit sound and affect the video:

1. Ensure that the Frame header is selected along with the sound track(s) you want to edit;



2. Proceed with the edit.

When using toolbar or menu functions to perform an edit, you can choose to include or exclude any track(s) from the edit in the following pop up box;



Removing Background Noise

You can remove background noise from a sound clip or an entire track



See Video

How to remove noise from a clip:

1. Select the track you want to change.
2. Click on the handle of the clip.




3. Right-click on the clip and select **Remove Noise**.

Or

Click **Sound** -> **Remove Noise** in the menu.

4. Set the strength of the noise removal;



5. Click **Apply Noise Removal**.

Fading a Clip In and Out

You can fade a sound clip in and also fade it out.



See Video


How to fade a clip in and out:

1. Select the track you want to change.
2. Select the clip you want to edit.
3. Right-click on the clip and select **Fade Clip In/Out**.

Or

Click **Sound -> Fade Clip In/Out** in the menu.

4. Set the duration of the fade in and/or fade out.



5. Click **OK**.

The fade in and out is displayed as a greyed out section on the sound clip;




Adding Sound

There are two ways to add sound to a video. You can add an existing sound file to your movie, or record sound from a microphone.



See Video

How to add an existing sound file:

1. Select the frame where you want to insert the sound file.
2. Click  **Add** on the toolbar.



Or

Click **Insert -> Sound** in the menu.

3. Browse to the file, select it and click the **Open** button.
4. Click **OK**.

The sound file has now been added as a new track.

How to record a sound clip:

1. Select the frame where you want the recording to start.
 2. Click  **Record** on the toolbar.
- Or
- Click **Sound -> Record Sound** in the menu.
3. Select which microphone to record with.
 4. Click **record**.
 5. Press the space bar or click  on the toolbar to stop recording.

The recording has now been added as a new track.

Adding Text and Images, Highlights, Arrows and Buttons




See Video (Text)



See Video (Images, Arrows and Buttons)

How to add text to a movie:


1. Select the frame where you want to insert the textbox.
2. Click  on the toolbar.

Or

Click **Insert -> Text** in the menu.


Adding Text and Images, Highlights, Arrows and Buttons

3. Set the properties of your textbox;




Adding Text and Images, Highlights, Arrows and Buttons

4. Set the appearance of the textbox;



5. Click **OK**.

How to add an image to a movie:

1. Select the frame where you want to insert the image.
2. Click  on the toolbar.


Or

Click **Insert -> Image** in the menu.

3. Click **Load Image**.


Adding Text and Images, Highlights, Arrows and Buttons

4. Browse to the image, select it and click **Open**.
5. Set the properties of your image;



6. Click **OK**.

How to add a highlight to your movie:


1. Select the frame where you want to insert the highlight.
2. Click  on the toolbar.

Or

Click **Insert -> Highlight** in the menu.


Adding Text and Images, Highlights, Arrows and Buttons

3. Set the properties of the highlight;



4. Click **OK**.


How to insert an arrow:

1. Select the frame where you want to insert the arrow.
2. Click  on the toolbar.


Or

Click **Insert -> Arrow** in the menu.

3. Set the properties of the arrow;




4. Set the appearance of the arrow;



5. Click **OK**.

How to add a button:


1. Select the frame where you want to insert the button.
2. Click  on the toolbar.

Or


Click **Insert -> Button** in the menu.

Adding Text and Images, Highlights, Arrows and Buttons

3. Set the properties of the button;



4. Set the appearance of the button;



5. Click **OK**,

Tips for better performance recording

You can improve your screen recordings by changing the recorder settings. You can increase the frame rate of the recording and change the recording type.



See Video


How to change the recorder settings:

1. From the BB FlashBack recorder, click **Tools -> Options** in the menu and click **Record Mode / Performance**.

Or

From the BB FlashBack player, click **Tools -> Recording Options** in the menu and click **Record Mode / Performance**.

2. Change the recorder settings;



3. Click **OK**.

For further guidance, please see the article at: <http://www.bbsoftware.co.uk/BBFlashBack/Support/UserGuides/recordingvideo.aspx>

Saving your recordings as Flash

You can export your movie as a Flash file or other types of video formats



See Video


How to export as Flash:

1. Click  **Export** on the toolbar.

Or


Click **File -> Export** in the menu.

2. Select the Flash option;



3. Click **OK**.

4. Select or change the Flash Export Options.



5. Click **Export**.
6. Choose where to save the exported files and click **Save**.

Three files are exported and you can choose view the export once completed. To view the movie in a web browser, ensure that you open the .html file that has been exported.


Creating Pan and Zoom Effects

You can zoom into a movie. Whilst the movie is zoomed in, you can add a pan effect or zoom out.



See Video


How to zoom in:

1. Select the frame where you want to add the zoom in.
2. Click  Add Zoom/Pan on the toolbar.


Or

Click **Effects -> Add ZoomPan** in the menu.

3. Set the properties of the zoom;




4. Set the size and position of the zoom;



5. Click **OK**


How to pan, while zoomed in:

1. Select the frame where you want to add the pan.
2. Click  Add Zoom/Pan on the toolbar.

Or

Click **Effects -> Add ZoomPan** in the menu.


3. Set the properties of the pan;



4. Click **OK**.

Click and drag the zoom/pan to set the pan destination.


How to zoom out from a previous zoom in:

1. Select the frame where you want to add the zoom out.
2. Click  **Add Zoom/Pan** on the toolbar.

Or

Click **Effects -> Add ZoomPan** in the menu.

3. Set the zoom to show the whole movie;



4. Click **OK**.


Using Autoscroll

You can crop the movie to a smaller size and add an autoscroll effect to still show all of the action.



See Video


How to add a cropping rectangle:

1. Click  on the toolbar.

Or

Click **Effects** -> **Set Cropping Rectangle** in the menu.

How to remove a cropping rectangle:

1. Click  on the toolbar.

Or

Click **Effects** -> **Set Cropping Rectangle** in the menu.

How to add an autoscroll:

1. Click **Effects**.
2. Go to the **Autoscroll Cropping Rectangle** submenu.
3. Click **Mouse In Centre**.

Or

Click **Mouse Near Centre**.

How to remove an autoscroll:

1. Click **Effects**.
2. Go to the **Autoscroll Cropping Rectangle** submenu.
3. Click **None**.

Recording from the Webcam

You can record a webcam whilst you record the screen or record only the webcam.



[See Video](#)

How to record the webcam whilst you record the screen:

1. From the BB FlashBack recorder, tick **Record Webcam**.


Or

From the BB FlashBack recorder, click **Tools -> Options** in the menu, then click **Webcam**, tick **Capture Video From Webcam** and click **OK**.

Or

From the BB FlashBack player, click **Tools -> Recording Options** in the menu, then click **Webcam**, tick **Capture Video From Webcam** and click **OK**.

2. Select the webcam to record with;



3. Click .

Please note, if you tick **Show Webcam Window While Recording** it will display the webcam video on screen while recording. The webcam video will be part of the recording and cannot be moved and resized in BB FlashBack player.

How to record the webcam only:


1. From the BB FlashBack recorder, click **Tools -> Options** in the menu, then click **Webcam** and tick **Capture Video From Webcam**.

Or

Recording from the Webcam


From the BB FlashBack player, click **Tools -> Recording Options** in the menu, then click **Webcam** and tick **Capture Video From Webcam**.

2. Tick **Record Only From Webcam And Not The Screen**;



3. Click **OK**.

4. Select the webcam to record with;



5. Click .

Note: The 'Record webcam only' function will create an FLV file instead of an FBR file.

How to insert a WebCam recording:


1. Select the frame where you want to insert the WebCam recording.
2. Click **Insert -> WebCam / Picture-In-Picture Video** in the menu.
3. Click **From FLV Video File**.

Or

Click From **AVI, WMV Video File**.

4. Browse to the recording, select it and click **Open**.


How to edit the WebCam recording:

1. Select only the WebCam track header and click  **Properties** on the toolbar.

Or

Double-click the WebCam image in the movie.

2. Set the WebCam video properties;



3. Click **OK**.

How to move or resize the WebCam recording:

1. Click and drag to move and resize the WebCam recording.


Adding Watermarks


You can add a watermark to on a movie.



See Video

How to add a watermark:

1. Click  on the toolbar.
- Or
- Click **Insert -> Watermark** in the menu.
2. Click **Load Image**.
3. Browse to the image, select it and click **Open**.
4. Set the properties of the watermark;



5. Click **OK**.


Inserting A Video File

You can insert video files into your movie.



See Video


How to insert video:

1. Select the frame where you want to insert the video.
2. Click  in the toolbar.

Or

Click **Insert -> Video File** in the menu.

3. Browse to the video file, select it and click **Open**.
4. Set the position and padding for the video:



5. Click **OK**.

Scheduled Recording

You can schedule a recording for a specific time, or for when a specific application is opened.



See Video


How to schedule a recording:

1. From the BB FlashBack recorder, click **Tools -> Options** in the menu, then click Scheduling.

Or

From the BB FlashBack player, click **Tools -> Recording Options** in the menu, then click **Scheduling**.

2. Tick **Use Scheduling For The Next Recording**.
3. Set the scheduling properties;



4. Click **OK**.

5. Click .

6. Click **OK**.


Cursor Highlighting

You can highlight the cursor and any mouse clicks in the movie.



[See Video](#)

How to highlight the cursor:

1. Click  on the toolbar.

Or

Click **Effects** -> **Highlight Cursor** in the menu.

2. Set the highlight properties;
3. Click **OK**.

Part III. User Guide

Professional Edition v4

Introducing BB FlashBack

BB FlashBack is a screen recorder - it makes movies of what you see on your PC screen.

Easy Recording

With only a few clicks of the mouse, BB FlashBack can record everything that happens on your Windows desktop. It can also record PC sounds or a commentary if you have a microphone.

If you have a webcam connected to your PC, BB FlashBack can record from it to produce 'picture in picture' movies.

For more details see [BB FlashBack basics](#).

Powerful Editing Features

BB FlashBack comes with a powerful editor application that you can use to add annotations and sound to your movie

For more details see [About Editing Movies](#).

Easy Upload to Video Sharing Websites

BB FlashBack makes it easy to share your movies by giving you easy upload to some of the most popular video hosting sites: YouTube, Blip.tv, Viddler and Revver.

For more details see [Uploading Movies](#).

Publish to Popular Formats

Movies can be exported to Flash, QuickTime (H264), Windows Media Video (WMV), GIF, AVI, MS PowerPoint or standalone EXE format. They can be viewed by virtually anyone with a PC or Internet Browser.

For more details see [About Exporting Movies](#).

Contacting Blueberry

Blueberry has years of experience in offering both custom software development and IT consultancy to clients that require a rare combination of technical expertise and an understanding of how this can address their business needs.

For more information about Blueberry and its products, go to our website: www.bbsoftware.co.uk [<http://www.bbsoftware.co.uk>]

For pre-sales and product support in your region:

1. Go to the Support menu - in the Help menu in Player, and main menu in Recorder.
2. Select the "Support for BB FlashBack" item and use the contact details shown.

System Requirements

Software Requirements

BB FlashBack runs on Windows 2000, XP, 2003, Vista, 7 and 2008. 32 and 64 bit versions supported. However Windows 2008 Server R2 does not support playback of recordings.

The capture driver (not required for recording, but may give better performance on older PCs) is certified for 32 and 64 bit versions of XP and Vista. It has been tested but not certified on Windows 2000 and 2003.

DirectX 7.0 is required to play back movies. If you see a warning message regarding your version of DirectX when you try to view a movie, you should browse to <http://www.microsoft.com/directx> and download the latest version of the DirectX runtime for your Operating System.

Windows 2000 users need to apply a hotfix to Windows before BB FlashBack will run. Go to <http://support.microsoft.com/kb/816542> and click 'View and Request Hotfix Downloads' near the top of the page to request the hotfix from Microsoft.

Export to Windows Media Video (WMV)

Windows Media Player 9 or newer needs to be installed in order to export to WMV format.

Export to QuickTime

QuickTime 7 or newer needs to be installed in order to export to QuickTime format.

Export to MS PowerPoint

MS Office 2000 or newer (including PowerPoint) must be installed in order to export to PowerPoint format.

Hardware Requirements

Processor speed: 500Mhz minimum, 1Ghz recommended

Memory: 256MB RAM minimum, 512MB RAM recommended

Display: Super VGA (800x600) or higher resolution

Graphics card: 8MB video memory required, 64MB and above recommended

Buying BB Flashback

To continue to use all the features of BB FlashBack beyond the 30 day evaluation period, you must purchase a licence key. You can do this either online or by phone.

Buying a licence

1. Start BB FlashBack

If you haven't already entered a licence key, you will see a window that gives you the option to "Buy BB FlashBack". Select that option. Or, use the menu item "Buy BB FlashBack Pro" in the Help menu in Player or the main menu in Recorder.

2. Buy a licence

When the online store page opens in your web browser, follow the instructions to buy a licence key. It will be emailed to the address you register with, so make sure this is your real email address.

3. Type the key into BB FlashBack

When you receive the key, you need to enter it into BB FlashBack. There are two ways to do this.

- If you've not already entered a licence key, you will see a window that gives you the option to "Enter Your Licence Key". Select this option and enter the key and owner name into the window that appears next. The owner name is case sensitive.
- Select the "Enter / View Your Licence Key" item from the Help menu in the Player or the main menu in the Recorder. Enter the key and owner name into the window that appears next. The owner name is case sensitive. Once you've entered the licence, it takes effect immediately.

Note: This process can be performed from either Player or Recorder. Entering the key once from either application licences BB FlashBack as a whole – the process does not need to be performed twice.

Problems with licence keys

I purchased online, but I didn't receive the email containing licence keys

When you register with Blueberry, it is essential that you provide a valid email address. We need this address to send you your registration licence keys to activate the product.

If you purchased BB FlashBack directly from Blueberry (not from a reseller), your licence keys are always available for viewing on our website. Login at <http://www.bbsoftware.co.uk>, then click the 'Your Account' button in the Welcome box on the right-hand side of the page. You will see a page showing details of your account. Now click "View licence keys you've already purchased" at the top of the page.

Also please note that despite our best efforts to prevent it, our mails may be caught by anti-spam software you are running. If you are expecting licence key information from Blueberry and it hasn't arrived, be sure to check your junk mail folder.

I'm having problems entering the key into BB FlashBack

To enter the licence key in BB FlashBack, start either the Player or Recorder program and select the 'Enter / View Licence Key' item from the Help menu in Player or the main menu in Recorder. In the next window, enter the Licence Key and Owner Name exactly as they appear in the email from Blueberry, or on our

web site, and click OK. We advise that you cut and paste the Licence Key and Owner Name values into the relevant fields, to eliminate typing errors.

Other help with key related problems

If you are still having difficulty receiving or entering your licence key, please email keys@bbsoftware.co.uk [<http://keys@bbsoftware.co.uk>] or contact your reseller with details of the problem.

Resellers

We have registered resellers in countries across the globe. If you prefer to use a reseller rather than buying from Blueberry direct, go to our online resellers list [<http://www.bbsoftware.co.uk/purchase/resellers.aspx>].

Getting Started

BB FlashBack Basics

There are two separate applications in BB FlashBack: the **Recorder** and the **Player**.

The Recorder

Records your desktop

It records what happens on your Windows desktop and saves this as a FlashBack movie file.

To learn more, see [Recording movies](#).

Records Sound

It also records sound - either the PC sounds, or a commentary if you have a microphone connected. If you're running Windows Vista, you can record a commentary and PC sounds at the same time.

To learn more, see [Recording sound \[93\]](#).

Records Webcam video

If you have a webcam connected, BB FlashBack can record from that as well, to show it picture- in-picture in the final movie.

To learn more, see [Recording Webcam video](#).

The Player

Plays back movies

It lets you play back, edit and add things to FlashBack movies, and save them as movie files that can be played by all PC users.

To learn more, see [Playing back movies](#).

Edits movies

You can edit out mistakes or add pauses with the frame editing functions.

To learn more, see [About editing movies](#).

Annotates movies with text and images

You can add textboxes, images, highlights or buttons to movies.

To learn more, see [Adding text boxes\[137\]](#) [Adding images \[139\]](#) [Adding highlights \[141\]](#) and [Adding buttons \[142\]](#).

Adds effects

You can add 'zoom and pan' type effects to have the movie focus in on an area of the screen.

Exports to other file formats

When you're done and want to show other PC users your movies, you can export to a number of file formats. See [About exporting movies](#).

To get started

You can record a movie using [BB FlashBack Recorder](#).

See [Recording movies](#).

Once you have recorded a movie you can view and edit it using [BB FlashBack Player](#).

See [Playing back movies](#).

When you want to share the movie with other PC users, [BB FlashBack Player](#) gives you the option of exporting it into a number of file formats. See [Sharing movies](#).

Recording movies

With only a few clicks of the mouse BB FlashBack can start to record everything that happens on your Windows desktop.

Select whether you want to record the full screen or just a region or window. Choose a sound source and webcam and click the button, and BB FlashBack records your desktop.

When you're finished, click the button and the recording is saved to a file you can open in BB FlashBack Player to edit, annotate and save in a standard video format.



To view the movie

For help on viewing your movie, see [Playing back movies](#).

For help on some of the more advanced features of BB FlashBack Recorder, see [About recorder features](#).

Playing back movies

Open BB FlashBack Player from the shortcuts on your desktop or Windows Start menu and play back movies by using the Open item on the File menu or the button on the toolbar.

From The Welcome Window

Starting either Recorder or Player shows the Welcome window:



Click 'Open an existing movie file' to select a recording and play it.

Playing a movie from Recorder

On the File menu of the Recorder main window, use the Open or Open Recent items to open a recording.


When Recorder is minimized to a tray icon or floating controls, show the main menu (by clicking the icon or clicking the button on the floating controls). Use the Play item or the recently recorded movies list at the top of the menu.

Sharing movies

If you want to share your movies with other PC or Mac users, you'll need to either upload them to a video hosting site or export them and send the exported file to the user.

Uploading to a Video Hosting Site

BB FlashBack can upload your movie to these video hosting sites: <http://www.youtube.com>, blip.tv [<http://blip.tv>] and <http://www.revver.com>. Use the Upload button on the Player toolbar.



You need an account at the video hosting site before you use this function. The first time you use this feature you'll need to give BB FlashBack your login details (it'll remember them for next time).

When the upload finishes you'll get a web address you can easily send to someone. When they open it in a browser they'll see a web page displaying the movie.

See [Uploading Movies](#) for more help.

Sharing Movies

If you want non-FlashBack users to see a movie you've created, you'll need to export it. Here are the file formats BB FlashBack can export to:

Flash

Flash is the easiest format to embed in a webpage. It includes full playback controls. A very high (>95%) of PC and Mac users should be able to view movies in this format. Flash and EXE formats are the only formats that support interactive elements like 'click to continue' textboxes and buttons. To learn more, see Exporting to Flash.

QuickTime (H264)

QuickTime uses advanced compression to achieve a good balance of quality and file size. QuickTime movies can be embedded in webpages and streamed to viewers. They will play back in all Mac's but only PCs that have QuickTime or iTunes installed. You need QuickTime 7 or later installed to export to QuickTime format. To learn more, see Exporting to Quicktime.

Windows Media Video (WMV)

As with QuickTime, you can achieve good quality and file size with this format, and WMV movies can be embedded in Web pages. WMV files should play back on virtually all PCs, but generally not on Macs. You need Windows Media Player 9 or newer to export to WMV format. To learn more, see Exporting to Windows Media Video.

Standalone EXE

BB FlashBack can export your movie as an executable file (EXE file) that plays the movie when opened. It has configurable playback controls, 'lossless' quality images and can achieve very small file size. The EXE file will only play back on Windows PCs. EXE and Flash formats are the only formats that support interactive elements like 'click to continue' textboxes and buttons. To learn more, see Exporting to Standalone EXE.

AVI

Exporting to AVI can be complicated for less technical users because a codec is needed to encode the movie. The image quality and file size is very dependent on the codec used. If a PC doesn't have the codec you used to encode it, it may not be able to play back the AVI file, and the codecs you can guarantee are installed on all Windows PCs may not give good results. To learn more, see Exporting to AVI.

MS PowerPoint (PPT)

BB FlashBack can save you movie as a PowerPoint file with the movie embedded in the first slide. You need MS Office 2000 or newer, including PowerPoint, to export to this format. To learn more, see Exporting to Powerpoint.

I want to send it to other BB FlashBack, BB FlashBack Express or BBTestAssistant users

Just send them the FlashBack Movie file (FBR file) created by BB FlashBack - they will be able to play it, and the FlashBack file is often smaller than other formats.

I want to display the movie on a webpage

The easiest way of displaying a movie on a webpage is by uploading to a video hosting site and using the "embed" code they provide for the movie. See [Uploading movies](#) for more details.

If you want higher quality and/or interactive elements in the movie, you need to export to Flash and copy that Flash export onto your web server. See [Displaying a Flash export on a webpage \[168\]](#) for more help.

WMV and QuickTime formats can also be embedded in web pages. See [Displaying a Quicktime movie on a webpage \[173\]](#).

I want to include the movie on a CD

Try exporting to Flash, QuickTime, WMV and EXE formats. The format that gives best image quality at lowest file size may depend on the content of your movie.

EXE format often gives smallest file sizes if 'normal' Windows applications are recorded. If your movie contains moving video or lots of photographic images, Flash QuickTime or WMV formats may produce smaller exports.

Using BB FlashBack

Recorder Windows

The Recorder Main Window

The Recorder main window allows you to easily change the main recording options and start recording



The Record setting allows you to select what to record.

- Full screen (or screens if you have more than one monitor)
- A Window
- A Region

Turn on the 'Record Sound' setting to record sound. You'll need to select a source, usually either PC Speakers or the Microphone, and you can set the recording levels. See [Recording sound](#) for more help.

Turn on the 'Record Webcam' setting to record from attached webcams. See [Recording webcam video](#).

Turn on the 'Minimize to tray/floating controls while recording' setting to minimise Recorder while it is recording. Select between minimizing to the icon tray or to floating controls by using the settings in the Tools menu.

The Recorder main menu

Show the Recorder main menu by minimizing Recorder to the icon tray and clicking the icon, or minimizing it to floating controls and clicking the button.

From this menu you can show the recording options window, record a new movie, create a report or play your recently recorded movies.

When you are recording a movie, this menu can be used to pause or stop recording. The menu items from top to bottom:

Recently recorded movie list

This list is always at the top of the menu. It shows the names of the previous ten movie files that you have created. Each file has a pop out menu that contains a number of options to enable you to play, edit or re-record it. For more help, see Movie file sub-menu.

Play

Displays a file selection dialog, then starts up BB FlashBack Player to show the selected movie.

Record

Starts a recording immediately, using the current settings.

Options

Shows the Recorder options window.

Pause (only enabled while recording)

Pauses recording.

Add Marker (only enabled while recording)

Allows the user to add a marker while recording. Recording is paused and a window is displayed where you can enter a marker name.

Restart Recording

Starts recording again. Everything recorded up to that point is discarded.

Stop (only enabled while recording)

Stops recording.

Help

Shows the help file within the application.

Support

Use the *Report Problem to Blueberry* item on this sub-menu to report to Blueberry any problems you have while using BB FlashBack. See Reporting problems for more help.

Buying BB FlashBack

Not displayed once purchased. Contains 2 items:

Buying a licence

Displays help on how to buy a licence.

Buy BB FlashBack online

Select this item to go to our online store. See Buying a licence for more help.

Enter/Review Licence key

Shows a window where you can enter the licence key and owner name you purchased from Blueberry to fully licence BB FlashBack.

Minimize to tray

Displays the Recorder as an icon in the system tray when minimised.

Minimize to floating controls

Displays Recorder as a floating toolbar when minimized.

Check for updates

Select this item to check on the internet for newer versions of BB FlashBack.

About

Displays the *About box*. This shows the program version number, licence key and enables registration and purchasing.

Exit

Closes the Recorder application.

The movie file sub-menu

Each item in the recently recorded movie list has a sub-menu. The menu items from top to bottom are as follows.

Open

Opens the movie in BB FlashBack Player and automatically plays the selected movie file.

Attach to new bug report

This option is only visible if you have installed BB BugReporter. Selecting this option starts up the Bug Reporter application, creates a new bug report and attaches the selected movie file.

Play Flash

Select this option to play the Flash movie that was previously exported from this movie file. If there has been no Flash export from the selected movie, this option will not be displayed.

Export To Flash

Select this option to export to a Flash movie file. For more help see Exporting to Flash.

Export to AVI

Select this option to export to an AVI movie. For more help see Exporting to AVI.

Export to WMV

Select this option to export to a WMV movie. For more help see Exporting to WMV.

Export to Standalone EXE

Select this option to export to standalone EXE format. For more help see Exporting to Standalone EXE.

Export to PowerPoint

Selecting this option to export to a PowerPoint file. For more help see Exporting to Powerpoint.

Send by email

Opens a new message in your default email client and attaches the movie in the selected format. There are 3 formats to choose from: native FlashBack FBR file, Macromedia Flash and AVI.

Re-record

Starts to record a new movie with the same name as the selected movie file. The selected movie file is overwritten and replaced with the new recording.

Remove from menu

Choose this option to remove the selected movie file from the recently recorded movies list.

Save As

Choose this option to save the movie to another file name.

Delete

Choose this option to delete the selected movie file and remove it from the recently recorded movies list.

Explore

Choose this option to open the folder containing the selected movie file in Windows Explorer.

Copy file path to clipboard

Copies the full path and name of the movie file as text into the clipboard.

The Recorder Options window

Use this window to adjust recording settings, such as display options, sound, webcam and other more advanced options.

These settings will be used the next time you select Quick Record or Record.

The Record Wizard will take these settings as its defaults.

More settings are available on the Recorder Options window than in the Record Wizard. To show the Recorder Options window:

From the Recorder main menu select *Options...*

or

On the Recorder main window select *Options* from the *Tools* menu.

The recorder options window contains the following tabs.

Display

Use this to set the Windows display settings during recording and how BB FlashBack windows appear during recording and in the final movie. For more help, see Windows display ptions.

Sound

Use this tab to select when sound will be recorded, and the format and compression that will be used.

Webcam

Select whether to record video from an attached webcam, and the device and format used. For more help, see Recording webcam video.

Keystrokes

Options relating to capturing of keystrokes are set on this tab. For more help see: Capturing keystrokes.

Hotkey

Select this to define a hotkey that can be used to make the recording controls pop-up window appear during recording. For more help, see Defining and using hotkeys.

File Size

Use this tab to select options to limit the size of the movie file produced. For more help, see Limiting the movie file size.

Record mode

Use this tab to change your recording mode or the number of frames captured per second. For more help, see Recording modes and Performance.

Misc

This tab contains settings relating to start-up options and the various delays that BB FlashBack inserts between certain operations at the start of recording. For more help, see Customising delays.

Advanced

This tab contains advanced settings relating mainly to performance.

Scheduling

Use these settings to have BB FlashBack record at a set time or when a certain application runs and closes. For more help, see Scheduled recording.

Adding a Marker while recording

While recording is in progress, you can add a marker by using a popup window.




To make the pop-up window appear during recording

1. Pause recording by selecting Pause from the Recorder main menu or using a hotkey (if defined - see Defining and using hotkeys).
2. Select 'Add Marker' from the Recorder main menu.
3. Enter a name into the Marker field.
4. Click Add to add the marker at that point in the recording.
5. Continue recording by clicking the Continue button.

Using Recorder when it is minimized

BB FlashBack Recorder can be minimized to the icon tray or to floating controls.



In the icon tray

Recorder appears as an icon in the system tray. Access its functions by clicking it and selecting from its popup menu.

Floating above the desktop

Recorder appears as a set of controls floating above the desktop. You can start to record, or play a movie, by clicking its Record and Play buttons. You can access the same menu as seen in Tray icon mode by clicking the 'down arrow' button. The toolbar can be positioned anywhere on the Windows desktop. Position it by clicking on the FlashBack logo on its left end and dragging.

Change how Recorder minimizes by selecting an option from the Tools menu.

Recorder features

About Recorder features

Recording sound

BB FlashBack can record a spoken commentary, via a microphone connected to your PC. See Adding and Recording Sound into a Movie.

Recording Webcam Video

If you have a webcam attached to your PC, BB FlashBack will record video from that at the same time as you record the desktop, and play it back 'picture in picture' style.

See Recording Webcam Video.

Recording windows, regions or full screen

BB FlashBack can do all three. See Recording windows and regions.

Recording multi-monitor systems

BB FlashBack can record from multiple monitors simultaneously into one movie. See Recording multi monitor systems.

Setting Windows display options while recording

To reduce the width and height of your movies, BB FlashBack can set a lower screen resolution during recording.

Windows graphic effects such as animating or fade-in menus can result in larger file sizes and slower playback on lower powered PC. These effects can be switched off during recording.

See Windows display options.

Continuous recording

BB FlashBack can record continuously and limit the size of the movie file produced. See Limiting the movie file size.

Recording modes

BB FlashBack has three different methods of recording screen changes. The best one to use will depend on your version of Windows and your PC hardware.

See Recording modes and Performance.

Setting hotkeys

BB FlashBack can respond to a hotkey during recording to display a pop-up controls window. See Defining and using hotkeys.

Recording windows and regions

BB FlashBack can record either the entire Windows desktop or only a single window or rectangular region. You choose whether to record the entire desktop or a region on the Recorder main window.

How to record a single window

1. Select *Window* in the Record setting on the Recorder main window.
2. When prompted, click the window you want to record - a red frame will appear around it.
3. Click Record.

The recording will be restricted to the area of the selected window.

Note: if you move the selected window the recorded area will not move with it, unless you turn on the 'Track window position while recording' setting on the Advanced tab of the Options window. If you resize the selected window during recording, the size of the movie does not change from its initial dimensions.

How to record a region

1. Select *Region* in the Record setting on the Recorder main window.
2. When prompted, size and position the red frame, then click Record.

The recording will be restricted to the area inside the purple frame.

Note: the size and position of the recorder frame window cannot be changed during recording.

Recording multi monitor systems

If you are running BB FlashBack on a multi-monitor system, it allows you to record from multiple monitors into one movie.

Note: 'capture driver' record mode can only record from the primary monitor.

- If you select to record 'One or more monitors' in the Record setting on the main window, before recording starts you'll be prompted to select the monitors to be recorded.
- If you select to record a window or region, it can span multiple monitors. Areas that fall outside of all monitors will be blacked out in the recording.

Windows display options

BB FlashBack can change Windows display settings while recording. Changing the settings may improve performance while recording and produce smaller files.

Improving Performance and Decreasing File Size

There are a number of graphic 'effects' that Windows uses to improve the appearance of its user interface. Having these effects switched on can affect the performance of your PC while recording a movie or playing it back. They will also result in a larger movie file.

BB FlashBack includes options to switch off these effects while recording. They are set back to their former settings when recording stops.

These effects include:

- The drop shadow under the mouse cursor.
- Menu and tool tip 'transition' effects, like fade-in and expanding menus.
- Gradient shading in window title bars.
- Smooth scrolling in combo and list boxes.
- The 'slide-open' effect in combo boxes.

There are also two other Windows settings that BB FlashBack can temporarily change while recording to improve performance:

- Desktop background bitmaps - BB FlashBack can set the desktop background to a single colour.
- Display of window contents while moving and resizing - BB FlashBack can set Windows to only display the window border while moving and resizing.

To turn off Windows graphic 'effects' during recording

1. On the Recorder main window, select Options from the Tools menu and go to the Display tab.
2. If Recorder is minimized to a tray icon or floating controls, show the main menu (click the tray icon, or click the button on the floating controls).
3. Select Options.

4. Select the Display tab.
5. Check the *Switch off Windows graphic 'Effects'* checkbox.

BB FlashBack will turn off graphic 'effects' when recording.

To set the background bitmap to a single colour or only show window borders when resizing, check the relevant boxes.

Capturing keystrokes

BB FlashBack can capture keystrokes during recording and display them in the Player application during playback. This can show the viewer actions performed by the user at record-time (such as pressing of function keys), which would not be obviously apparent by just viewing the movie.

Because this feature could inadvertently display the characters used in a password, by default BB FlashBack can blank out these password characters with asterisks.

Note: BB FlashBack cannot 'asterisk-out' passwords entered into password fields in web pages or in Remote Desktop sessions. The characters are saved into the keystroke log and can be seen in the KeyLog viewer in BB FlashBack Player.

How to switch on keystroke recording

1. In the Recorder Options window, go to the Keystrokes tab.
2. Check or uncheck the *Capture Keystrokes* box accordingly.
3. Use the *Replace Password Characters* checkbox to hide or show password characters when keystrokes are captured.

For help on viewing keystrokes during playback, see Viewing key presses.

Limiting the movie file size

BB FlashBack can limit the size of the movie file created.

By default no limit is set, but you may wish to enable this option so that BB FlashBack can record continuously without gradually filling up all available disk space.

There are two modes to select from.

Limit by time

Select this option to have BB FlashBack create movie files that only contain a set number of minutes.

For example: you select this option and set the maximum minutes recorded to 5, and then record for 10 minutes. The final movie file will contain the most recent 5 minutes of recording.

To set the number of minutes that BB FlashBack will record in a single movie file

1. Open the Recorder Options window and then select the *File Size* tab.
2. Select the *Limit by time* radio button.
3. Enter a value into the *Limit To* entry field. This is the number of minutes that BB FlashBack will record into a single movie file.

Limit by size

Select this option to have BB FlashBack create movie files that never exceed a certain size.

For example: you select this option and set the maximum movie file size to 5Mb. The final movie created will be approximately 5Mb in size or smaller (if you did not record long enough to reach the limit).

To set the maximum size of a movie file

1. Open the Recorder Options window and then select the *File Size* tab.
2. Select the *Limit by size* radio button
3. Enter a value into the *Limit To* entry field. This is the maximum size of a single movie file

Defining and using hotkeys

BB FlashBack Recorder will let you define a hotkey combination. This has two uses:

- During recording, pressing the hotkey will cause the recording pop-up window to appear. From this window you can stop, pause or restart the recording.
- While BB FlashBack Recorder is running in the system tray but not recording, pressing the hotkey will cause the Recorder Options window to appear.

To define a hotkey

1. Open the Recorder Options window.
2. Select the Hotkeys tab
3. Put the cursor in the *Hotkey* field and press the key combination that you want to assign to the hotkey. The *Hotkey* field will display the combination
4. Click *OK*

BB FlashBack Recorder will now respond to that hotkey.

Customising delays

There are two customisable delays that can be set on the BB FlashBack Recorder options window:

1. The delay between clicking a button or menu item on BB FlashBack recorder to record and the actual start of recording.
2. If you have selected to change the screen display mode during recording, BB FlashBack can insert a delay between this change and the start of recording.

During both of these delays, a small 'initialising' window is shown.

To change the customisable delays

1. Open the Recorder Options window and then select the Misc. tab.
2. To set delay 1, change the value in the *Delay before recording* field. To set delay 2, change the value in the *Delay after changing screen mode* field.

Recording Webcam Video

If you have a webcam attached to your PC, BB FlashBack lets you record video from it while recording the screen. You can include the webcam video in your movies and exports.

For more help on viewing webcam video and including it in your exports, see [Viewing webcam video](#).

How to record video from a Webcam

1. On the main Recorder window, turn on the 'Record WebCam' setting or on the Recorder Options window, select the WebCam tab and turn on the 'Capture video from webcam' setting

2. Select the device you want to capture video from
3. Click the Settings button to change the size of the webcam video and set the brightness, contrast etc

Note: You will not see the webcam video on your screen while recording - you will see it later when playing back the movie in BB FlashBack Player.

Record modes and performance

Set the record mode on the Record Mode tab of the Recorder Options window. BB FlashBack has three recording modes.

- **GDI** - this is a general-purpose mode that works well on a variety of PCs and situations, on all versions of Windows.
- **MPEG** - this mode is best at recording moving video. However, lower powered PCs will struggle to record large desktops at a high frame rate with this mode.
- **Capture driver** - this gives high performance when recording 'normal' Windows applications that don't contain animation or moving graphics. On older PCs in particular it may give better performance than other modes. It cannot record Vista Aero mode.

'Auto' Mode

BB FlashBack also has an 'auto' mode that tries to pick the best mode for your PC and situation. If it detects a media player application running, it will select mpeg mode if your PC is capable of running it at a good frame rate. If no media player is detected, or your PC isn't powerful enough to run mpeg mode, it selects GDI mode. If your PC isn't powerful enough to use GDI mode, capture driver mode is selected.

For Vista and Windows 7 users

GDI and MPEG modes can record Vista / 7 'Aero' graphics mode. Capture Driver mode will force Windows into 'basic' graphics mode during recording, but may give better performance and smoother movies than GDI mode when recording Windows 'basic' graphics.

Setting the frames per second

When using GDI or MPEG modes you can adjust the frames recorded per second. A higher frames per second (FPS) value means the final movie should be smoother, but may affect the performance of your PC while recording. A lower FPS value means that your PC will perform better during recording, but movements in the final movie will be less smooth. BB FlashBack will try to set a sensible default FPS value, but the ideal rate depends greatly on what you are trying to record, so you may achieve better results by experimentation.

Troubleshooting poor performance

See Troubleshooting video recording for more help.

Troubleshooting video recording

We've worked hard to ensure that BB FlashBack can record your screen at a good frame rate. However, because of the widely varying capabilities of different PCs and video cards it is possible that some users will be unable to make high quality recordings of certain applications.

Poor quality / jerky motion when recording moving video

- Ensure you are using MPEG mode, not GDI or capture driver mode.
- Record just the movie player window, not the entire desktop.
- Experiment with the FPS setting on the Record Mode step of the wizard. You may actually get a smoother recording by decreasing the FPS because this reduces CPU load.

Recording media/movie player type applications results in a black rectangle in the recording where the video should be

This is due to the movie player program using 'overlays' - a hardware video acceleration feature that cannot be recorded. You will need to force the program to not use overlays by either using a setting in BB FlashBack or changing a setting in the movie player itself.

On Windows XP

On the Record Mode step of the Record wizard, click the More Settings button. On the More Settings window, turn on the 'Disable hardware acceleration' feature. Before recording starts, BB FlashBack will prompt you to click a button and disable hardware acceleration.

Note: to record some media player applications, you will need to start them after hardware acceleration is disabled, so that they don't try to use overlays. And to record some movie players (e.g. KM Player) you will need to change their settings manually so that they do not use overlays, because they do not detect that use of overlays is disabled.

On Windows Vista or 7

To record the movie player you will need to find a setting in that application that disables its use of hardware acceleration or overlays. The name of the setting will vary from application to application.

Capture driver mode is disabled after installation

Sometimes the driver requires Windows to be rebooted before it is available for selection. If Capture Driver mode is disabled on the Record Mode step or Options window, this may be the reason.

If you see a message about ASUS software when installing BB FlashBack and running the Recorder, BB FlashBack has detected software that is incompatible with the driver, and not installed it. See this FAQ entry.

How to email Blueberry technical support

If you are experiencing difficulties with recording modes and performance, you can email our technical support team for help.

1. Open the Recorder Options window and select the Record modes tab.
2. Click the Troubleshooting button and select Send email to support.
3. In the wizard, describe your problem as fully as you can. If you want a response to your report, include your email address.

The wizard will send an email directly to our technical support team. Details of your PC specification are attached, but this does NOT contain any personal information - just a description of your PC hardware.

Recording sound

While recording Windows desktop activity, BB FlashBack can also record sound via a microphone attached to your PC. This soundtrack is saved into the movie file.

How to turn on sound recording

You can check the 'Record sound' box on the Recorder main window, or on the Sound tab of the Recorder Options window. The recorder main window gives you access to the main settings, while the Sound tab of the Recorder Options window enables access to more advanced settings.

The Sound Device

BB FlashBack will choose the default sound device automatically. For most PCs this is sufficient, but for those with more than one sound card, you may need to select a non-default device. Go to the Sound tab of the Options window and select the device.

The Sound Source

Microphone Select this to record a commentary from an attached microphone. Use the Level slider and volume indicator on the right of the window to ensure that your microphone is connected and picking up sound correctly. If BB FlashBack does not detect a suitable microphone source attached to your selected sound device, this option will not be enabled.

PC Speakers

Select this option to record what you hear from your PC speakers. A typical sound device (e.g. a sound card) will have a number of 'sources' available for recording. Click the Select Sources button to see the sources that play through your PC speakers. You can select which sources to record and adjust their relative volumes with the mini-sliders.

Other Sources

On the Options window these will be in the 'Other Sources' section. In the main window these will be in the Source dropdown list. You may find the 'stereo mix' source here, which can be useful for recording the PC Speakers, or PC Speakers and Microphone together, on Windows XP.

Recording the PC Speakers and Microphone together

On Windows Vista and 7, just select the PC Speakers source as the main source you are recording. On the main window, select Microphone as the 'Second Source'. On the Options window, select 'Record Microphone into a separate track'.

On Windows XP, recording the PC Speakers and Microphone is only possible if your sound card enables it, and many do not. You should consult any documentation that came with the card, and look at settings in the driver software that installs with the card. This is usually in the Windows Control Panel, or your desktop icon tray (bottom right of the desktop by default).

Try selecting the 'Stereo Mix' source which may be listed as an 'Other source' on the Options window or the main window.

Sound Formats

You can select sound formats on the Options window but not the main window. Selecting different sound formats will vary the quality of the recording and the amount of space it occupies in the movie file. You can select:

Sample rate

The higher, the rate the better the sound quality but the more file space the sound track occupies.

Stereo / Mono

Stereo will give better sound quality than mono, but also produce larger movie files.

MP3 compression - This option should always be selected unless you are experiencing problems or crashes during recording or export. Deselecting this option may greatly increase the movie file size. BB FlashBack uses a redistribution of the LAME MP3 codec: <http://www.mp3dev.org>.

Troubleshooting sound recording

We've tried to make it as easy as possible for you to record sound, either from an attached microphone or the sounds made by the PC. However, due to the widely varying audio capabilities of different PCs and sound cards, some users may experience problems.

Problems recording the Microphone

If you are having problems trying to record sound from a microphone:

Make sure you have a suitable microphone connected to the correct input of your PC sound card

1. On the BB FlashBack sound settings window (go to Tools > Options > Sound tab), select the 'microphone' radio button.
2. On the same window, set the 'Level' slider up as far as it will go. Now speak into the microphone. The green and red 'Level' indicator on the right side of the window should move. If the level indicator moves, it shows BB FlashBack Recorder is detecting the sound. If it does not move, no sound is being detected from your microphone sound channel and you should follow the steps below to check that the microphone is operating correctly.
3. Again on the same window, select the *PC sounds* option and click the *Select sounds to mix* button. Make sure that the 'microphone' source is enabled and its volume slider positioned at the right. Test again by speaking into the microphone and seeing if the Level indicator moves with the sound volume.

Try to record the microphone using the Windows Sound Recorder

1. Open the recorder from the Windows Start button -> Programs -> Accessories -> Entertainment -> Sound Recorder.
2. Select the *Audio Properties* item on the *Edit* menu.
3. Click the *Volume* button for the *Sound Recording* device.
4. Ensure that the 'microphone' source is selected on the Recording Controls window.

5. Back in the Sound Recorder, click the *Record* button and speak into the microphone.

6. Click *Stop* and the << button, then replay.

If you do not hear your recording, your PC and Windows are not set correctly to allow recording from the microphone. If you do hear your recording, now try and record with BB FlashBack, using the microphone as the sound source.

Check that you are able to use the microphone in other applications like Skype and MSN Messenger

If you can use the microphone properly in other Windows applications and still can't record sound from the microphone in BB FlashBack, click the *TroubleShooting* button on the *Recorder Options* window *Sound* tab (BB FlashBack Recorder > Options > Sound tab). This will let you send an email to Blueberry Technical Support team. Please give as much information about the problem as possible, and indicate whether you have gone through the hints above.

Problems recording PC Sounds

We've tried to make it as easy as possible for you to record sound, either from an attached microphone or the sounds made by the PC. However, due to the widely varying audio capabilities of different PCs and sound cards, some users may experience problems.

Dell PC Owners

If you are having trouble recording PC sounds, this is probably because it has been deliberately disabled on your PC. This is to prevent copyright violation and is performed by a number of manufacturers, in particular Dell.

The solution will probably be technical in nature, involving editing the registry and/or installing new drivers, and may be specific to your particular PC model.

We recommend searching for "dell --your pc model-- cannot record sound" and seeing if a solution exists.

If you are having trouble recording PC sounds

- Make sure 'PC Speakers' is the selected sound source. On the Sound tab of the Recorder Options window, select the PC Speakers option. The coloured 'level' indicator on the right should move when sounds are played back through the PC speakers or headphones. If indicator does not move, your sound recording settings need to be changed - see step 2 below
- Make sure the 'stereo mix' or 'wave' sources are selected. Click the Select sounds to mix... button on the Sound step or tab. This displays the 'PC Sound Sources' window which shows the sources selected for recording. Make sure the 'stereo mix' and 'wave' sources are selected and their volume sliders set to the right. Check whether BB FlashBack is now recording PC sounds correctly by playing back sounds and watching the level indicator. If it moves, sounds will be recorded. If not, try step 3 below. Note: some PCs required you to select the Stereo Mix source using a program that is installed with the sound drivers - BB Flashback cannot do it. You will find the sound utility program in the Windows Control Panel, and it should have a name like "SoundMax" or "SigmaTel Audio."
- Try 'other sources'. In some PCs the correct sound source is not visible in the 'PC Sound Sources' window. On the Sound step/tab again, select the Other Sources radio button and select 'Stereo mix' or 'wave' (try both) from the drop down list, if available. Again, test by playing sounds and watching the level indicator on the BB FlashBack sound setup window.

- Update the drivers for your sound card. Updating or reinstalling sound card drivers can enable PC sounds recording.
- Search the internet. Sometimes you'll need a fix specific to your PC. Use a search engine to search for your make and model of laptop or (if you have a desktop PC) sound card, and "cannot record pc speakers."

Some PCs and laptops cannot record PC sounds by design - it is deliberately disabled to prevent copyright violation. You may be able to enable it by making changes to the registry or installing a different version of the sound card drivers. However, it is impossible to record PC sounds on some PCs.

This page describes how to download alternative drivers that fix the problem on Dell Latitude and Inspiron laptops:

<http://www.ekhoury.com/2006/08/25/sigmatel-stereo-mix-support-for-dells/>

This page describes a fix for Inspiron laptops, but it involves editing the registry. Be warned: you could disable your sound card or worse if you make a mistake when editing the registry.

<http://forum.notebookreview.com/showthread.php?t=156400>

Alternatively, search for your PC model and "cannot record pc speakers" - the solution may be out there.

Problems with Audio-Video synchronisation

Some PCs may encounter problems with audio-video synchronization, particularly with longer movies. These problems are highly dependent on the particular sound hardware in your PC.

You can run a test in BB FlashBack Recorder that will enable options to correct sound sync problems.

1. Go to the Sound tab of the Recorder Options window.
2. Click the Sync Test button.

The test will take around 30 seconds to run. If it finds sync problems it will enable the 'Extra Sound Synchronization' option (found on the Advanced tab of the Recorder Options window). Using this option means there will be a delay on stopping recording while sound is processed and compressed.

Scheduled recording

BB FlashBack can start and stop recording at scheduled times. It can also start and stop recording when a specified application starts and closes.

To start and stop recording at set times

1. Open the Recorder Options window and select the Scheduling tab
2. Turn on the 'Use scheduling' setting
3. Set the start time in the 'Start At Time' setting and the stop time in the 'Stop at time' setting
4. Exit the Options window and start Recording as normal

After clicking the Record button you will see a message informing you that the next recording is scheduled. The Recorder main window will remain open or minimize as usual, and recording start at the set time.

After making a scheduled recording, the setting is turned off, so the next recording is made as normal, without scheduling.

To start and stop recording when an application starts and closes

1. Open the Recorder Options window and select the Scheduling tab
2. Turn on the 'Use scheduling' setting
3. Turn on the 'If specific application appears' setting. This means BB FlashBack will look for the specified application to appear and when it does, start recording

If the application does not appear before the specified start time, BB FlashBack starts to record at that time anyway.

You can specify the application to watch for either by giving some text that will appear in its title bar, or its executable name (e.g. iexplore.exe for Internet Explorer).

If you turn on the 'Record only this application' setting, the recording has the dimensions of the entire desktop, but everything except the application being recorded is blacked out.

Record-time Notes

BB FlashBack allows you to type notes while recording, and display these Notes in textboxes in the final movie.

How to turn on Record-time Notes:

1. In the Recorder Options window, go to the Record-time Notes tab and turn on the 'Enable Notes' setting.
2. The Notes settings:
 - You display the Note window by moving the cursor a side of the screen. Set which side activates Notes with the 'Show Notes window when mouse moved to' setting.
 - Recording can automatically pause while the Note window is displayed, so its not shown in the movie. Set this with the 'Pause recording when Notes window appears' setting.

- You can save the Note either by moving the mouse cursor out of the Note window or by clicking a 'Save' button on the window. Set this with the 'Auto-save note when cursor leaves the window' setting..
- Textboxes can be automatically created from your Notes when the recording is opened in BB FlashBack Player. Set this with the 'Auto-generate textboxes when the recording is opened' setting.

Viewing Notes in BB FlashBack Player


If you turned on the 'Auto-generate textboxes' setting, you will see your notes as textboxes in the movie. These are normal textboxes, so they can be edited and moved as usual.

If 'Auto-generate textboxes' was set off, you can view Notes in a pane to the Left of the movie. If left side pane has been hidden, you can display it again by going to View -> Extras Pane -> KeyLog in the Player menus.

The Player

The Player window

Use this window to play back and edit your movies.



The different parts of the main BB FlashBack Player window:

Menus

The functions on each menu are described in this help document. See the topics inside The Player Main Menu.

Toolbars

The various toolbars provide quick access to some of the most commonly used functions. For a description of their functions, see topics inside The Player Toolbars.

Timeline

The Timeline, together with the Frame bar, shows the position in the movie of the currently selected or playing frame. The Timeline is marked in either seconds or frames.

Framebar and objects

The Framebar shows each frame of the movie as a selectable rectangle. The selected frame is drawn in red. Selecting a frame causes it to display in the Movie area. Objects like textboxes and images that you've added to the movie are shown under the Framebar.

Sound Tracks

If your movie contains sound, each sound track is shown as a bar under the framebar. There may be a number of sound tracks.

Movie area

The Movie area fills most of the Player window, and this is where the movie appears as it is played.

Gallery

This area holds textboxes, images and other objects you can drag into your movie. You can also add your own textboxes etc into the Gallery.

Status bar

This is divided into four sections. The right-hand section shows the total length of the movie. The second-from-right section shows the value of any keys pressed during the recording of the selected frame. The other two sections display messages to inform a user of the status of BB FlashBack when it is engaged in operations that may occupy a noticeable length of time.

The Timeline and Frame bar

The Timeline

The Timeline shows the entire length of the movie, from the first frame on the far left to the final one. You can jump to any point in the movie by clicking on the Timeline. To help you navigate around, position your mouse over the Timeline to display a thumbnail image of the movie at that point.

It is marked in either seconds or frame numbers. The timeline units can be changed with the help of the Timeline Units option under the View main menu.

The Frame bar

The Frame bar contains a graphical display of each individual frame in the movie, starting with the first frame at the left through to the final frame at the far right. Each frame is shown as a selectable rectangle. Either a single frame or a continuous range can be selected and then modified by an edit operation.

You can regard the framebar as showing a magnified portion of the timeline.

Because each frame lasts only a short period of time (1/25th second by default) the Frame bar will typically only show a small portion of your movie.


Clicking on the Timeline selects a point in time and the frame at that point. The Frame bar will automatically scroll to show the selected frame, which is displayed in red.

For more help on selecting frames using the Frame bar, see [Selecting frames \[133\]](#).

For more help with frames see [About frames](#).

More about the frame bar

Shown below is a portion of a Frame bar and Timeline. The Timeline is marked in seconds.



The frame bar is drawn in a number of strips, to show Zoom-Pan effects, mouse clicks and keys pressed in a particular frame.


How to show or hide the Frame bar and Timeline

1. On the Player menu bar select View

2. Check or uncheck the menu items for Timeline and Frame bar to show or hide those items

Viewing Objects

When you add an object like a textbox or image to the movie, a bar in the 'Objects' section represents it.




In the above, a textbox appears, then an image.

The length of the bar represents the duration of the object.

Double click the bar to open the Properties window for that object. Click and drag the bar to change the point in the movie where it appears. Click and drag the end of the bar to change its duration.

Viewing Zoom-Pan effects

The example image above shows a Zoom-Pan effect. A Zoom-Pan effect looks like this in the framebar.



See Zoom-Pan Effects to learn more about this feature.

Viewing mouse activity

The middle slice of the frame bar shows mouse activity.

If the frames in this bar are coloured blue, this means that the mouse cursor is hidden in these frames. For more on hiding the mouse, see [Hiding the mouse cursor \[151\]](#).

The position of the dot is an indicator of where the mouse pointer is in the frame. The colour of the dot indicates whether it was moved or clicked.

- Gray: The mouse was not moved.
- Black: The mouse was moved.
- Red: The mouse was clicked.

Viewing key presses

See the help topic [Viewing key presses](#) for more information on this feature.

Webcam / Picture-in-Picture Video

BB FlashBack can show picture-in-picture video within the main screen recording.

You can record an attached webcam while recording the screen, and this webcam video will appear picture-in-picture when you open the recording in BB FlashBack Player. Or, you can import an FLV, AVI or WMV video file to be used as picture-in-picture video.

For more help on recording webcam video, see Recording webcam video.

How to import a video file as picture-in-picture video

1. Select the frame where you want the video to start.
2. Select an item in the WebCam / Picture-in-Picture Video submenu of the Insert menu.
3. Select a video file. It will be imported as picture-in-picture video at the current frame.

Note: because of the huge number of codecs available, not all AVI files can be imported successfully.

WebCam Video Display Modes

You can display webcam video in the movie in one of two ways.

In its own window

In this mode, the webcam video is shown in a window with its own title bar. This window can be moved anywhere on the desktop, independent of the main BB FlashBack Player window. When in this mode, the webcam video will not be included in exports.

Embedded in the movie

In this mode, the webcam video is shown in a frame inside the movie. It cannot be moved outside of the movie. The frame colour and thickness can be set via the webcam video properties window. When in this mode, the webcam video will be included in exports. Or you can hide the webcam video completely. Use the 'Show webcam video' item on the *View* menu to show and hide the webcam video window.


How to set the mode of the webcam video

Double click the webcam video window to show its Properties window.

Select a mode on the Properties window.

Editing Webcam Video

Webcam video is shown in a separate bar in BB FlashBack's framebar display. This enables you to include or exclude Webcam video in selections and therefore have edit operations act on it or not, as preferred. Toggle the selection of webcam video by clicking its header on the right.



The Player Toolbars

The File Toolbar

The File toolbar provides one-click access to some commonly used functions.

How to show or hide the File toolbar

1. On the Player menu bar select the View menu and the Toolbars item.
2. Check or uncheck the File toolbar item to show or hide the File toolbar.

The Player toolbar

The Player toolbar provides one-click access to some commonly used functions.

How to show or hide the Player toolbar

1. On the Player menu bar select the View menu and the Toolbars item.
2. Check or uncheck the Player toolbar item to show or hide the Player toolbar.

The Edit toolbar

The Edit toolbar provides one-click access to some commonly used functions.

How to show or hide the Edit toolbar

1. On the Player menu bar select the View menu and the Toolbars item.
2. Check or uncheck the Edit toolbar item to show or hide the Edit toolbar.

The Effects toolbar

The Effects toolbar provides one-click access to some of the effects functions.

How to show or hide the Effects toolbar

1. On the Player menu bar select the View menu and the Toolbars item.
2. Check or uncheck the Effects item to show or hide the Effects toolbar.

The View toolbar

The View toolbar provides one-click access to some of the view functions.

How to show or hide the View toolbar

1. On the Player menu bar select the View menu and the Toolbars item.
2. Check or uncheck the View item to show or hide the View toolbar.

The Sound toolbar

The Sound toolbar provides one-click access to some sound functions.

How to show or hide the Sound toolbar

1. On the Player menu bar select the View menu and the Toolbars item
2. Check or uncheck the Sound item to show or hide the Sound toolbar

The Objects Toolbar

The Objects toolbar provides one-click access to some commonly used functions.

How to show or hide the objects toolbar

1. On the Player menu bar select the View menu and the Toolbars item.
2. Check or uncheck the Objects toolbar item to show or hide the toolbar.

The Player Main Menu

The File menu

Record New Movie	Shows the Record Wizard to record a new movie.
Open	Opens a movie file.
Close	Closes the current movie file.
Save	Saves changes to the current movie file.
Save As	Saves the current movie file to a different name.
Save selected frames as movie	Saves the selected frames as a new FlashBack movie file.
Save frame as bitmap	Saves the current frame as a bitmap.
Export	Exports the movie as one of the supported file formats.
Batch Export Utility	Opens the batch export tool, which enables exporting of a number of FlashBack movie files to AVI or Flash formats.
Upload	Uploads the movie to a video hosting service or FTP server.
Manage Upload Profiles	Enables creation and editing of upload 'profiles'. A profile contains a server type and location, and your login details.
Properties	This displays information on the current movie
Copy to clipboard	Copies the movie file name to the clipboard.
Send by email	Opens a new email with the movie or an export attached.
Recently opened movies	
Exit	Closes the BB FlashBack Player application.

The Edit menu

Undo	Undoes the previous edit operation, rolling back to the state before that edit.
Redo	Redoes a previously undone edit operation.
Select frames	Enables selection of frames between two frame numbers.
Select all frames	Selects all frames in the movie.
Select inactive frames	Selects 'inactive' frames adjacent to the current frame. Inactive frames are frames with no mouse, keyboard or screen activity.
Delete Frames	Deletes one or more frames.
Crop Frames	Cuts the movie down to the currently selected frames, deleting all unselected frames.
Insert Frames	Inserts a new frame after the currently selected one.
Merge Frames	Merges a number of frames into one.
Bring to front	Moves the currently selected textbox or image in front of all other objects in that frame.
Bring forwards	Moves the currently selected textbox or image 'up' in the ordering of objects layered on top of the movie.
Send to back	Moves the currently selected textbox or image behind all other objects in that frame.
Send backwards	Moves the currently selected textbox or image 'down' in the ordering of objects layered on top of the movie.
Copy Object	Copies a selected object (textbox, image, highlight or button) to the BB FlashBack clipboard. Select an object by clicking it in the movie area.
Paste Object	Pastes any previously Copied object into the current frame.
Object Properties	Edits properties of the currently selected textbox or image.
Delete Object	Deletes the currently selected textbox or image.
Delete WebCam Video	Removes the WebCam video stream from the movie.
Edit ZoomPan	Shows the ZoomPan properties dialog on which you can edit the transition speed. Enabled if a zoompan object is created in the selected frame.
Delete ZoomPan	Deletes the zoompan. Enabled if a zoompan object is created in the selected frame.
Pause Graphic	Check this item to have a pause graphic displayed whenever the movie reaches a pause point, at a textbox or image. The sub-items allow you to specify the graphic used and where it is positioned. Set Pause Graphics allows you to select a graphic file that will be displayed whenever the movie is paused during playback. Set Default Pause Graphics sets the pause graphic back to the default supplied with BB FlashBack. Set Pause Graphics Position allows you to set the position that the pause graphic will appear in.
Markers	Current Markers list is a list of all of the markers in the movie. Selecting a marker from this list will jump straight to that frame. Delete shows a sub-menu containing the names of each of the markers in the current movie. To delete a marker, select it from this sub- menu.

The Insert menu

FlashBack Movie	Inserts a FlashBack (.FBR file) movie at the current frame.
Text	Adds a text box, which will appear at the currently selected frame.
Marker	Adds a marker to the current frame.
Image	Adds an image to the current frame.
Arrow	Inserts an arrow into the current frame.
Button	Adds a button to the current frame.
Highlight	Adds a highlight to the current frame.
Sound	Adds a sound file as a new track, starting at the current frame.
	Adds a watermark image to the movie.
Pause	Adds a pause to the current frame.
WebCam / Picture-in-picture video	Allows you to import an FLV, AVI or WMV movie file as a picture-in-picture or WebCam video.
Video File	Inserts a video file into the movie, starting at the current frame.
Blur	Inserts a blue effect into the movie. For more help see Adding a Blur Effect [145].
Mouse Clicks	Inserts a mouse click event at the selected frame.

The View menu

Timeline	Shows or hides the Timeline.
Frame bar	Shows or hides the Frame bar
Status bar	Shows or hides the Status bar
Toolbars	There are 4 sub-items on this menu item to show or hide the Edit, File, Player and Clipping toolbars.
Timeline Units	There are 2 sub-items on this menu item to select the units displayed in the Timeline: seconds or frames.
Timeline thumbnail	Selects the size of the thumbnail movie frame displayed when the mouse is over the timeline or frame bar.
KeyLog	Displays the KeyLog window, which shows all key strokes recorded in the movie.
KeyBar mode	Selects between 2 modes of displaying the keystrokes: Raw shows every keystroke in the frame it occurred. Sentence groups keystrokes together as words.
Movie Size	The sub-items on this menu item control the displayed size of the movie. By default a movie will be displayed at 100% - the original size. It can be shown at a smaller size by selecting an option of less than 100%. Other shows a dialog box where you can enter any percentage size for the movie to be displayed at.
Fit Movie to Window	Select this option to increase or decrease the size of the movie to fit into the BB FlashBack Player window as it is currently sized.
Fit Window to Movie	Select this option to increase or decrease the size of the BB FlashBack Player window so that it fits to the current size of the movie.
Full Screen	Selecting this option to have the movie area occupy the entire Windows desktop, with the toolbar positioned above it. All other parts of the Player interface are hidden.
Full Screen View	Sets which parts of the user interface will be visible in Fullscreen mode. By default only the timeline is visible. By checking items in this submenu, you can make the framebar and toolbars visible.
Auto-scroll	There are 3 options in the Auto Scroll submenu. Select None to turn Auto-scrolling off. If the movie is larger than the movie area, you may need to scroll manually to see everything of interest. Select Mouse in centre to have BB FlashBack scroll the movie area to keep the mouse in the centre. Select Mouse near centre to have BB FlashBack scroll the movie area to keep the mouse near the centre.
View PC information	Movie files recorded by BB TestAssistant [http://www.bbsoftware.co.uk/bbtestassistant.aspx] include information about the PC that recorded the movie. Select this menu item to see that information.
View external log files	Displays logfiles generated by external programs - only available for movie files recorded by BB TestAssistant [http://www.bbsoftware.co.uk/bbtestassistant.aspx].
View Movie in Separate Window	If you have multiple monitors, select this option to have the movie shown fullscreen in a non-primary monitor, and the toolbar, framebar, timeline and other controls on the primary monitor.

Switch WebCam Mode	WebCam can either be shown in a separate window or embedded in the movie. Use this menu item to switch between the two modes.
Show WebCam Video	Use this item to toggle webcam video visibility.

The Movie menu

Play	Starts playback or continues when paused.
Playback Speed	Sets playback speed to x4, x2, normal, 1/2 or 1/4 speed.
Forward	Moves to the next frame.
Back	Moves to the previous frame.
First Frame	Moves to the first frame in the movie
Last Frame	Moves to the last frame in the movie
Prev Marker	Moves to the previous frame containing a marker.
Next Marker	Moves to the next frame containing a marker.
Prev Mouse Click	Moves to the previous frame containing a mouse click event.
Next Mouse Click	Moves to the next frame containing a mouse click event.
Loop	Check this option to have the movie play continuously in a loop.
Pause on	<p>There are 4 sub-items on this menu item:</p> <ul style="list-style-type: none">• Pause on Mouse Clicks: Check this option to have the movie pause playback on every frame that contains a mouse click.• Pause on Markers: Check this option to have the movie pause playback on every frame that contains a marker.• Pause on Text boxes: check this option to have the movie pause playback on every frame that contains the appearance of a Text box. For more help on Text boxes see About Text boxes.• Ignore Pauses in Movie: check this option to ignore any pauses that may already have been inserted into the movie.
Goto Frame	Enables you to jump straight to a particular frame or point in time in the movie.
Search for Text	Use this option to jump to the frame where some specific text is drawn in the movie. It can be used to search for the text drawn in window title bars, so you could use it to find the frame where an application appears.

The Sound menu

Add New Sound Track	Add a new sound track.
Add Sound	Add a sound file to the selected frame.
Record Sound	Record sound into the movie.
Mute Sound	Mute the selected sound.
Increase Sound Volume	Increase the volume of the selected sound
Decrease Sound Volume	Decrease the volume of the selected sound
Volume Level Processing	Two functions to equalize volume in a movie: <ul style="list-style-type: none">• Make multiple clips have the same loudness (normalization)• Even out the volume in a clip (Compression)
Remove Noise	Removes background noise from the audio.
Fade Clip In/Out	Fades the volume of the selected clip in and/or out.
Split Sound Clip	Split the clip into 2 or 3 clips at the selected point.
Merge Sound Clips	Merge selected clips into one.
Merge Sound Tracks	Merge selected tracks.
Copy Sound	Copy selected sound.
Cut Sound	Cut selected sound.
Paste Sound	Paste sound.
Sound Options	Sets the default playback device and how MP3 sounds are edited and exported.

The Effects menu

Apply ZoomPan and Cropping Effects	ZoomPan and Cropping effects can either be unapplied, so you can edit them, or applied, so you can see how they change the appearance of the movie.
Add ZoomPan	Adds a ZoomPan effect to the current frame.
Add Transition	Adds a Transition to the current frame. It will create a transition from the previous frame to the current one.
Set Cropping Rectangle	Allows the user to position and resize the cropping rectangle.
Play in Cropping Rectangle	Restricts movie play back to only show what is within the cropping rectangle.
Make Cropping Permanent...	Permanently alters the movie so that it only contains what is within the current cropping rectangle.
Highlight Cursor	Set the mouse cursor highlight properties - the size, colour and opacity of the circle that surrounds it, and whether clicks are highlighted with circles.
Display Invisible Keystrokes	Automatically creates textboxes showing 'invisible' keystrokes like function keys. See Displaying Invisible Keystrokes for more help.
Start/End Titles	Adds 'titles' - text and/or image on a solid background at the start or end of the movie. See Start and End Titles for more help

The Tools menu

Player Options	Sets the sound playback device, whether BB FlashBack automatically checks for updates and other options.
Recording Options	Shows the Recorder options window.
Extract FBR from EXE Export	Takes an EXE exported from BB FlashBack and extracts and saves the FBR file it was originally exported from - EXE exports contain the FBR file.
Convert AVI file to FlashBack movie	Opens an AVI movie and converts it to a FlashBack (.FBR) movie file.

The Action menu

Hide / Show WebCam in selected frames	Sets webcam visibility in selected frames.
---------------------------------------	--

Mouse Cursor submenu

Bring cursor to front	Puts the mouse cursor in front of other in-movie objects such as textboxes and images.
Send cursor to back	Put the mouse cursor behind other in-movie objects.
Hide cursor in selected frames	Hides the cursor during movie playback for those selected frames.
Show cursor in selected frames	Shows the cursor in the selected frames if it has previously been hidden.
Re-record mouse cursor	Enables you to re-record mouse movements. <ul style="list-style-type: none">• In selected frames• For the whole movie
Smooth Cursor Movements	Corrects mouse movements for a selection of frames so that it move smoothly from its position in the first frame to its position in the final frame of the selection.
Reset mouse action images	Uses the default or your own custom animations in place of mouse action animations saved in the movie.

Cropping submenu

Set Cropping Rectangle	Allows the user to position and resize the cropping rectangle.
Play in Cropping Rectangle	Restricts movie play back to only show what is within the cropping rectangle.
Make Cropping Permanent...	Permanently alters the movie so that it only contains what is within the current cropping rectangle.

Movie Speed submenu

Speed up selected frames	Use this option to speed up playback of part of the movie by a selectable factor.
Slow down selected frames	Use this option to slow down playback of part of the movie by a selectable factor.

Select Inactivity submenu

Define Inactivity	Allows you to define an 'inactive' section as the absence of annotation, mouse movements and/or key presses.
Select Next Inactive Section	Selects the next inactive section from the current frame.
Select Previous Inactive Section	Selects the previous inactive section from the current frame.
Delete all Inactive Sections	Deletes all inactive sections from the movie.

The Help menu

BB FlashBack Help	Displays the help file.
Support	BB FlashBack includes functions to allow you to report problems with the application to Blueberry Software. Enable/Disable logging auto-run - switches on internal logging for BB FlashBack. Report Problem to Blueberry - displays a wizard that directs you through the process of sending a problem report to Blueberry.
Buying BB FlashBack Pro	Not displayed once purchased. Has 2 sub items: Buying a licence - displays help on buying a licence Buy BB FlashBack Pro - opens a page on the Blueberry website where you can buy a licence online.
Enter/review licence key	Displays a window where you can enter or review the licence key and owner name given to you by Blueberry to fully licence BB FlashBack.
Check for update	Checks for a newer version of BB FlashBack. If one is found, you will be given the option to download and install it.
About	Displays the About box, which displays the BB FlashBack version numbers, shows email and web links for support and allows you to enter a license key.

Viewing key presses

BB FlashBack offers two ways of viewing keys pressed during recording of the movie: the Key logging window and the KeyBar.

The key logging window

This shows a display of all keys pressed while the movie was being recorded. You can search for a specific word and jump to the frame in which it is typed.

How to display the Key Logging window

From the Player, select the KeyLog item from the View menu.

The Key Logging window can either float above the movie area, or be 'docked' to the side of the movie area. Use the 'Dock' and 'Undock' buttons to select the configuration you prefer.

Viewing modes

There are two ways that the window can show key press data: "Raw", which shows all key presses in a sequence and "Sentence" which groups together presses into words and lines, and is more easily readable.

Sentence mode attempts to simplify the display by showing you the results of edits and corrections. For example, if a user mistyped "Treasure" as:

Treasure

And then corrected the word by hitting backspace three times and retyping "ure", you would see in the Key logging window, in Sentence mode:

Treasure

BB FlashBack has combined the key presses together. However, it can only do this for simple cases, where the backspace, arrow and delete keys are used.

Additionally, each key press or sentence can be displayed with a "timestamp" - the time, relative to the start of the movie, that the item was typed.

How to search for a word typed within the movie:

1. On the Key Logging window, type the word or part of a word into the Search for field.
2. Click the Search button. BB FlashBack will look through all the key presses in the movie for that word and jump to the frame where the first letter of that word was typed.

The Auto-locate feature

If the Auto-locate box is checked, as your cursor moves through the Key Logging window, BB FlashBack will always jump to the frame in which the letter at the cursor was pressed.

Exporting key press data

Press the Export button to have BB FlashBack can export the key press data, in either raw or sentence format, to XML.

The KeyBar

The KeyBar is a section of the Framebar that shows the keys pressed in any frame.

Viewing modes

There are two ways that the KeyBar can show key press data: "Raw", which shows all key presses in a sequence and "Sentence" which groups together presses into words and lines, and is more easily readable.


Here is an example of the same word ("test") typed during the movie and viewed in Raw then Sentence mode.

In Raw mode it looks like this:



You can see the frame in which each of the letters was pressed.

In sentence mode, the key presses are grouped together into a word, and the KeyBar shaded in blue to show the duration of the word:



So Raw mode gives a more 'detailed' view of the key presses, but Sentence mode is easier to understand.

To change key view modes

Go to the Key Log Mode item in the View menu.

More on sentence mode

Sentence mode attempts to simplify the display by showing you the results of edits and corrections. For example, if a user mistyped "Treasure" as:

Treasire

And then corrected the word by hitting backspace three times and retyping "ure", you would see in the Key logging window, in Sentence mode:


Treasure

BB FlashBack has combined the key presses together. However, it can only do this for simple cases, where the backspace, arrow and delete keys are used.

More on Raw mode

Where there is more than one key pressed in a single frame, Raw mode draws the frame with a small green indicator. To see all the key presses in the frame, put the mouse over the frame to show its thumbnail image. The keys are listed under the image.

In the example below, the 't' and 'e' keys were pressed in the same frame. I put the mouse over the frame to see the thumbnail.



Virtual Keys

In both Raw and Sentence views, virtual keys such as arrow keys, modifier keys (e.g. Ctrl or Alt) and function keys are shown in blue. In the example above, the small blue triangle shows when the space key was pressed.

Here is a list of virtual keys and how BB FlashBack represents them in the KeyBar.

▲	Space
⇧←	Left tab
⇧→	Right tab
↵	Return
⇧↑	Left shift
⇧↓	Right shift
←	Left arrow
→	Right arrow
↑	Up arrow
↓	Down arrow
⊞	Windows key
Del	Delete
Ins	Insert
Esc	Escape
BkSp	Backspace
Ctrl	Ctrl
Alt	Alt
CpLk	Caps lock
NmLk	Num lock
ScrLk	Scroll lock
PgUp	Page up
PgDwn	Page down
Home	Home
End	End
Pause	Pause
Brk	Break

Other Player Features

The Player Options window

The Player Options window holds some extra settings used by BB FlashBack Player. To display the Options window, Select the Player Options item from the Tools menu.

Playback options

- Use the Return to start of movie checkbox to have the Player return to the start frame of the movie on reaching the end. If this option is not selected, the Player displays the final frame when the movie ends.
- Use the Auto play check boxes to have the Player automatically start to play a movie when it is opened from the Open menu or by double clicking its icon in Windows.

Update options

- Select the Automatically check option to have BB FlashBack check for newer versions of itself every day. If this option is not selected, you will need to check for updates manually. See Checking for updates to BB FlashBack for more details.
- Select the Help us improve BB FlashBack by... option to have BB FlashBack send back usage data when it checks for updates.

Note: this information is sent completely anonymously. It's a huge help to us at Blueberry to know if BB FlashBack is crashing, which features are being used and whether there have been installation problems. This data will may well influence future development.

Sound options

- Select the sound device to be used for sound playback in the Player.
- Set the 'common' MP3 compression level used for sound files are added to the movie via the Insert sound menu item or toolbar button.

Advanced options

Use the Memory usage options to change the amount of memory used by BB FlashBack. If it uses more memory, it is faster at seeking to random frames in the movie when the timeline is clicked during playback.

Converting AVI files to FlashBack movies

BB FlashBack allows you to convert an AVI video file to a FlashBack format movie (.FBR file). You can open the converted file in the Player, to add text, sound, edit frames etc. as normal.

Note: the compression used in FlashBack movie files is optimised for recording normal Windows applications, not moving video. If you convert an AVI of a TV show, for example, the resulting FlashBack movie file will probably be much larger than the original AVI.

Note: this function is only tested and supported for AVI files encoded using these codecs: Full frames (uncompressed), Huffiyuv, DivX 3 & 5, MS Video 1, Techsmith Screen Capture.

To convert an AVI file to a FlashBack movie file

1. In Player, select Convert AVI file to FlashBack movie from the Tools menu.
2. Set the AVI filename field to the AVI file that you want to edit in BB FlashBack.
3. Set the FlashBack filename field to the name of the FlashBack file you want to create.
4. Check the Open movie after conversion checkbox if you want to open the converted movie for editing straight after the conversion has completed.

Command-line options

The player can be invoked from the command line as follows:

Flashback Player.exe [/option] <movie name>

Here option is facultative, and movie name is necessary. If no option is provided, the movie is simply played. You can specify one of the following options:

- /e — open for edit.
- /f — export to SWF.
- /v — export to AVI.
- /? or /help — display a list of available options.

Editing Movies

About editing movies

Once you've recorded a movie, BB FlashBack enables you to edit the video and sound, and add annotations in the form of text, images and sound to enhance the viewing experience.

Annotations

You can add text boxes, images, buttons, highlights or sounds to a movie. For more details see [About Text Boxes \[137\]](#) [Adding Images \[139\]](#) [Adding Highlights \[141\]](#) [Adding Buttons \[142\]](#) [Adding Sound to Movies, Adding Arrows \[143\]](#), [Adding a Watermark \[145\]](#) & [Adding a Blur Effect \[145\]](#).

Frame Editing

You can delete or insert frames. For more details see [Working with frames](#).

Zoom and Pan Effects

You can zoom into any area of the movie to better show the details and focus the viewer's attention. See [Zoom-Pan Effects](#).

Sound

You can add sound files or record a new sound track for a movie. You can also edit sounds in the movie. To learn more, see [Working with Sound](#).

Cropping

You can use the cropping functions to view and export a smaller area than was originally recorded. For more details see [About Cropping](#).

Pauses

You can add pauses to a movie, so that playback will stop at a particular point until the viewer indicates it should proceed. For more details see [Inserting a pause in the movie](#).

Working with frames

Just like a conventional movie you might watch at the theatre or on TV, a FlashBack movie is a series of still frames played in a sequence.

BB FlashBack's frame editing functions let you fine-tune the movie by removing sections, adding blank frames to create pauses or tidying up how big changes appear in the movie.

How the framebar and timeline work

The framebar and timeline controls allow you to select single or multiple frames, so an edit function can operate on them. To learn more see [The Timeline and Frame bar and Selecting Frames \[133\]](#).

Deleting frames

Use the Delete frames function to remove mistakes or anything unwanted. See Inserting and deleting frames [134].

Creating a pause by inserting frames

Use the Insert Frames function to create pauses and slow down the action. See Inserting and deleting frames [134].

Enhancing the appearance by merging frames

The Merge frames function merges all the changes in a series of frames into one. This can be useful in tidying up sections where Windows was slow to display applications or draw the contents of a window. See Merging Frames [135].

Selecting frames

The various edit operations operate on either a single frame or a continuous range of frames. For example, Add text will add a text box to a single frame and merge frames combines a range of frames into one.

At any time there is one current frame. This is marked in red on the Frame bar and its image is shown in the movie area below.

How to select a single frame


Selecting single frames is simple – just click with the left mouse button on the Framebar or Timeline to display a frame in the movie area and highlight it in red on the Frame bar.

How to select a range of frames

There are 2 ways of selecting a range of frames.


- Hold down the Shift key while clicking the start and end points of the range. You can click either the framebar or the timeline to define the range in this way.
- Click the start or end frame in the range and while holding the mouse button down, drag the cursor across the framebar or timeline to define the range.

BB FlashBack shows the selected frames in red.



You can include selections in the framebar and soundtracks, so an edit operation acts on the same range across multiple sound tracks and the movie frames.

If your movie includes webcam video, you can also include or exclude that from the selection by clicking the webcam header.



See More about selecting sound and frames.

How to move the start or end of a range

Keeping the Shift key pressed down, click on a frame in the Frame bar again. If the frame you clicked is nearer the start of the range than the end, BB FlashBack will now make the range start at that frame. Conversely, if the frame you clicked is nearer to the end of the range, BB FlashBack will now make the range end at that frame.

By keeping the Shift key pressed down and clicking on the Frame bar, you can change the start and end frames of the range.

How to quickly view the start and end frames of a range

By holding down the Ctrl key and pressing the left and right arrow keys, the current frame will switch between the start and end of the range. As usual, the current frame is highlighted in red on the frame bar and shown in the movie area. This can be useful when merging a range of frames for example, to make sure that the range starts and ends at exactly the right points.

How to select inactive frames

If there are a sequence of frames that contain no interesting activity, and you need to delete, you can use the Select inactive frames function.

Select a frame in the inactive sequence, then select the Select inactive frames menu item from the Edit menu. This will select all frames with no keyboard, mouse or screen activity that are adjacent to the current frame.

Inserting and deleting frames

To delete frames from a movie

1. Select either a single frame or a range of frames. For more help on selecting frames, see Selecting frames [133].
2. On the Player main menu, select Edit and then Delete Frame(s).

Or

On the Edit toolbar, click the Delete button.

Note: the Delete function also deletes any selected sound. For more on selecting sound and frames together see More about selecting sound and frames.

Inserting Frames and Pauses

The insert frame function creates one or more duplicates of the currently selected frame. The effect of this is to create a pause in the movie, which could be used (for example) to ensure that specific events are synchronised with the appearance and disappearance of text boxes.

To insert a frame into a movie

1. Select a single frame.
2. On the Player main menu, select Edit and then Insert Frame(s).

Or

On the Edit toolbar click the Insert Frames button.

3. In the Insert Frame(s) window input the number of new frames to insert or the length of the pause in 1/1000ths of a second and click 'Ok'. The duplicate frames will be inserted after the selected frame.

Note: if you insert a pause at a point where a sound is playing, you will be given a choice of either inserting silence into the sound (to keep it in sync with later events in the movie) or leaving the sound unchanged. You indicate this with the 'Insert silence into sound track' checkbox.

Merging Frames

The merge frames function can be useful in tidying up the appearance of a movie.

An example of how to use the Merge frames function:

An application is recorded starting up, which comprises many separate, complex windows. In the movie, the individual windows do not seem to appear at the same moment, but are visibly drawn separately, across a number of frames.

To improve the appearance of the movie and have all the windows appear together in just one frame, you could merge the range of frames that starts just before the first of the windows appears and ends just after the last one is fully drawn. Merging means that all of these frames get combined into one, and the windows all appear together.

Merging does not affect the overall length of the movie. All of the merged frames appear identically in the resulting movie.

How to merge a range of frames

1. Select a range of frames. For more help on selecting frames, see Selecting frames [133].
2. On the Player main menu, select Edit and then Merge Frames or on the Edit toolbar, click the Merge Frames button.

Cropping frames

BB FlashBack includes a function to remove all but the selected frames from the movie.

How to crop the movie down to only the selected frames

1. Select the range of frames that you want the movie to consist of.
2. On the Player main menu, select Cropping frames from the Edit menu.

Or

On the Edit toolbar, select the button

Frame rates

The frame rate of a movie can be set using the Properties dialog. This frame rate is used in normal playback and is used as the default when exporting movies.

How to set the frame rate of a movie

1. In Player, select the Properties item from the File menu.
2. On the Frame Rate tab set the frame rate value appropriately. The default is 25 frames per second. There may be occasions when you wish to reduce this value to improve playback on lower spec PCs.

Annotating movies

Adding Text boxes

How to add a text box

1. Select the frame where you want to add a text box.
2. On the Player main menu, select Text from the Insert menu or on the Edit toolbar, click the Insert Text button.
3. On the Text box properties [138] window type the words you want to appear, select the style of the text, the box it appears in, and the length of time you want the text box to appear in the movie.

How to edit the properties of a text box

There are a number of ways to show the Text Box properties window for a particular text box.

- Double-click the text box itself, in the movie area.

or

- Click the text box in the movie area. A blue line will appear around the box to indicate it is selected. Then either select *Text box properties* from the *Edit* menu, or click the button on the *Edit* toolbar.

or

- Double-click on the frame in the Frame bar that contains the image to indicate the appearance of that text box.

Once the Text Box properties window is visible, the text content and style can be altered. For more help on this window see The Text Box properties [138] window

Changing text box direction

Text boxes only appear in the movie for a set length of time – the duration that was set in step 3 above on the Text box properties window. In the Frame bar you will see an image in the frame where you added the text box and an image in the frame where it is hidden. These mark the start and end of its appearance in the movie. You can change its duration by setting it in the Text box properties window, or by clicking and dragging the icons in the frame bar - you have to click, hold for a second and then drag.

How to move a text box

With the mouse over the text box in the BB FlashBack Player movie area, hold down the left mouse button. The cursor will turn into a shape and, keeping the left mouse button held down, you can drag the text box around the movie area to a new position.

Alternatively, the *Position* tab of the Text Box properties window allows you to enter the co-ordinates of the top left corner of the box.

How to resize a text box

This is done in the same manner as resizing a normal window. In the BB FlashBack Player movie area, move the mouse cursor over a corner or side of the text box – the cursor will change shape to indicate that you can drag that side or corner to resize the box.

Alternatively, the *Position* tab of the Text Box properties window allows you to enter the width and height of the text box in pixels.

How to delete a text box

1. Select the text box by clicking it.
2. On the Player main menu, select Edit and then Delete text.

or

On the Edit toolbar, click the Delete object button.

Pausing the movie at a text box

Movie playback can be automatically paused when a text box appears, giving the viewer time to read the contents of a text box before allowing the movie to continue. To enable this feature for a particular text box, bring up the text box properties window and check the checkbox titled 'Pause the movie at this text box...'.

The Text Box properties window

The text box properties window is used to change the text shown in a text box, the style in which it is drawn, the style of the enclosing box and whether the movie will pause at that box during playback.

There are 5 tabs on this window.

Properties

Enter the text to appear in the text box in the *Text* entry field. The font used and style of the box can be set using the controls on this tab. See Text box styles below for more information on styles. The length of time that the box will appear during the movie is entered in the *Text Duration* entry field. If you want movie playback to pause when this text box appears, check the *Pause movie at this text box...* checkbox.

Styles

Allows you to save the current look of the textbox as a 'style' that you can apply to other textboxes.

Background

The controls on this tab determine the colour of the text box background and border. You can set the box to have a gradient fill - a transition between two colours - from top to bottom or left to right.

Position

This tab contains controls for the exact positioning of the text box. The pixel position of the top left corner, and the width and height of the box can be entered.

Shadow

Select 'draw shadow' to have the text box cast a shadow over the movie below. Set the colour, size and opacity of the shadow using the controls on this tab.

Transitions

Have the textbox fade in and out by setting the duration of its transitions.

Text box styles

When you have a combination of text box properties - the colour, text size, font etc. - that you like and want to use again, you can save these properties as a style. Then you can apply this style to any other text box in any of your movies, to get the same appearance.

How to save a style

1. Get the text box properties as you want them.
2. On the Properties tab of the Text box properties window, click the *Save current style* button.
3. Enter a style name and click OK.

BB FlashBack creates a style with the name you entered. The style name will now appear in the *Select text box style* drop down list whenever you edit a text box, in any of your movies. To apply this style to a text box, just select the style name from the *Select text box style* drop down list.

The size and position of a text box is not saved in the style.

Adding Images

BB FlashBack can display images in the movie area.

How to add an image file to a movie

1. On the Frame bar, select the frame where you want to add an image
2. On the Player main menu, select Image from the Insert menu.

Or

On the Edit toolbar, click the Insert image button

3. Click on the 'Load Image' button to select an image file. Valid formats are .jpg .png .bmp .gif .emf .wmf or .ico files.

How to edit an image

There are a number of ways to show the Image properties dialog for a particular image.

- Double-click the image in the movie area.

or

- Click the image in the movie area. A blue line will appear around it to indicate it is selected. Then either click the button on the Edit toolbar or select Image Properties from the Edit menu.

or

- Double-click on the frame in the Frame bar that contains the icon to indicate the appearance of that image.

The Image properties window allows you to change:

Size and Position

The image can be sized as required, to stretch or shrink the original image.

Opacity

Sets the opacity of the entire image.

Transparent colour

You can select to have one colour in the image as transparent: i.e. that colour will not be drawn, and the movie area below will be visible through that pixels of the image that contain the colour. The 24 bit PNG and 32 bit (ARGB) BMP image formats can include alpha channel (transparency) information, so you can select to use that instead of setting a transparent colour.

Duration of display

The image can either be displayed for a set period of time or the movie can pause when it is displayed.

Transitions

Have the image fade in and out by setting the duration of its transitions.

How to move an image

With the mouse over the image box in the movie area, hold down the left mouse button. The Cursor will turn into a shape and you can drag the text box around the movie area to a new position. Alternatively, the position can be set via the Image properties dialog.

How to change how long the image is displayed for

You can either:

- Change the duration in the Image properties window

or

- In the framebar, click and drag the icons that signify the start and end frames of an image - you have to click and hold down for a second, then drag.

How to delete an image

Select the Image by clicking it on the movie area.

On the Player main menu, select *Edit* and then *Delete Image*. **or** On the *Edit* toolbar, click the *Delete Object* button:

Adding Highlights

BB FlashBack Player can add highlights to a movie during editing, to draw attention to an area of the movie.

How to add a highlight

1. Select the frame where you want to add a highlight box.
2. On the Player main menu, select Highlight from the Insert menu.

or

On the Player toolbar, click the Highlight button.

3. In the Insert Highlight window, three tabs allow the highlight to be customized.

General tab

Type the Name of the highlight; select the Shape of the highlighted area, its Fill Colour and Outline Colour. You can also choose the thickness of the highlight in pixels, its opacity and duration up to a maximum of 1 second. The duration can also be set to pause the movie until the mouse button is clicked.

Position tab

The Position tab allows you to enter the co-ordinates of the top left corner of the highlight.

Transitions tab

Have the highlight fade in and out by setting the duration of its transitions. In the Frame bar you will see an image in the frame where you added the highlight. Further highlights can be added to the Frame bar by right clicking the time line and selecting Insert Highlight. In the toolbar, the Jump to dropdown menu allows you to jump straight to a highlight.

How to edit the properties of a highlight

There are a number of ways to show the highlight properties window for a particular highlight.

- Double-click the highlighted area itself.

or

- Right click the highlight in the movie area and select Properties.

Highlights can also be layered in front of or behind other elements on the screen by right clicking over a highlight and selecting the 'bring forwards' and 'send backwards' type options from the menu.

How to move a highlight

The highlight appears by default at the top left of the recorded screen. Click the highlight and hold the mouse button down to drag it anywhere in the movie area.

Alternatively, the Position tab of the Image Insert properties window allows you to enter the co- ordinates of the top left corner of the highlight.

How to resize a highlight

Put the cursor at the edge of the highlight. It will turn into a resize cursor, and you can click and drag to resize the highlight.

Alternatively click the Position tab in the Image Insert window and entering the width and height of the highlight in pixels.

How to change how long the highlight is displayed for

You can either:

- Change the duration in the Highlight properties window.
- or**
- In the framebar, click and drag the icons that signify the start and end frames of the highlight - you have to click and hold down for a second, then drag.

How to delete a highlight

1. Select the highlight by clicking it
2. On the Player main menu, select Edit and then Delete highlight.**or** Right click the mouse over the highlight and select Delete.

Pausing the movie at a highlight

Movie playback can be automatically paused when a highlight appears, giving the viewer time to view the highlighted area before allowing the movie to continue.

To enable this feature for a particular highlight, bring up the Image Insert window and check the checkbox titled 'Pause movie until mouse clicked...'

Adding Buttons

Button objects are interactive objects that allow you to open a web page, jump to any point in the movie, start or stop playback.

How to add a button

1. Select the frame where you want to add a button
2. On the Player main menu, select Button from the Insert menu.

or

On the Edit toolbar, click the *Insert Button* button:

3. On the Button properties window:
 - a. Type the button caption
 - b. Select the style of the text and the button background
 - c. The length of time it should be displayed
 - d. The action. Available actions are:
 - i. Stop playback
 - ii. Start playback
 - iii. Open a URL. Enter address of the webpage, with or without the "http://" prefix. When the button is clicked, the web address will open in the default web browser.
 - iv. Jump to a point in the movie. You can jump to a frame number, marker or an object, such as a textbox, image, highlight, sound or button.
 - v. Execute Javascript. You can enter javascript that will be executed when the button is clicked. Note that the javascript will not be executed when playing the movie in BB FlashBack Player. It is only executed by the Flash export of the movie. There is a 400 character limit for the javascript code, but if you need to execute something more complex than this will allow, you can make calls to functions in the webpage that embeds the Flash export.

How to change how long the button is displayed for:

You can either:

- Change the duration in the Button properties window
- or**
- In the framebar, click and drag the icons that signify the start and end frames of a button - you have to click and hold down for a second, then drag.

Adding Arrows

BB FlashBack can add Arrows to the movie, to help focus attention on a detail.

How to add an Arrow:

1. Select the frame where you want to add an arrow.
2. On the Player main menu, select Arrow from the Insert menu.

or

On the Player toolbar, click the Arrow button.

Changing the Arrow appearance

To change the properties of an Arrow you can either:

- Double-click the Arrow.

or

- Right click the Arrow and select Properties.

In the Arrow properties window, you will see these tabs:

Properties

Settings here enable you to change:

- The shape at the start and end of the arrow
- The width of the tail and head
- Its opacity
- How long it is displayed for

Appearance

Settings here enable you to change:

- The fill type (lineart or gradient) and colour
- The border appearance
- The shadow appearance

Position

Settings in this tab enable you to change the position and size of the arrow.

Transitions

Here you set how the arrow fades in and out. Arrows can be layered in front of or behind other elements on the screen by right clicking over a highlight and selecting the 'bring forwards' and 'send backwards' type options from the menu.

Changing the arrow position and size

To move the arrow, click and drag its centre. To change the position of the tail or head, click and drag the tail or head. To make the arrow wider or narrower, change the 'Width' property on the Properties tab of its Properties window.

How to delete an Arrow

1. Select the arrow by clicking it.
2. On the Player main menu, select Edit and then Delete Arrow.

or

Right click the selected arrow and select Delete.

Adding a Watermark

BB FlashBack allows you to add a watermark image to a movie. This image remains with the position and size you set for the duration of the movie.

Note: The watermark cannot change its size and position during the movie.

How to add a watermark

1. In the Insert menu, select Watermark.
2. Select an image file.

To change the position of a watermark, you can click and drag it to anywhere in the movie area. To change its size, position the cursor over one of its edges or corners, then click and drag.

Adding a Blur Effect

BB Flashback can add a blur effect to obscure details in the movie. You might use this to obscure sensitive details in a form.

How to add a Blur Effect

1. Select the frame where you want to add the blur.
2. On the Player main menu, select Blur from the Insert menu.

Or

On the Player toolbar, click the Blur button .

You can adjust the strength of the blur by right clicking it, selecting Properties and changing the 'Blur Radius' setting.

Using the Gallery

BB FlashBack enables you to easily reuse textboxes, images and other objects by adding them to the Gallery. Once in the Gallery, they can be added to any movie just by dragging them in.

How to add an Object to the Gallery

- You can hold down the Ctrl key and drag the object into the Gallery.

Or

- Right click on the object and select "Add to Gallery" from the menu.

How to copy an object from the Gallery to the movie

- Drag the object from the Gallery into the movie.

Or

- Right click the object in the Gallery and select 'Add to Movie'.

You can edit an object in the gallery by double clicking it.

You can remove an object from the gallery by right clicking it and selecting 'Delete' from the menu.

Zoom-Pan Effects


BB FlashBack allows you to "zoom in" to any area of the movie, to more clearly show what's happening on screen.

How to zoom in

1. Select the frame where you want the zoom effect to occur.
2. Click the Add Zoom-Pan button on the toolbar.
3. On the Zoom-Pan properties dialog, select 'Custom Area' and click OK.

You'll see a green rectangle on the movie area. This marks the area that the movie will zoom into. Whatever is in the green rectangle will expand to fill the entire movie area.

The green rectangle will look like this:



You can move the green rectangle by clicking and dragging on the handle at the top left corner. Resize it by dragging an edge or corner.

How to preview your Zoom-Pan effect

Click the 'Apply Effects' button on the toolbar to see how the movie will look when exported. When effects are applied, you see no green rectangle.

Click the Apply Effects button again to turn effects off and see the green rectangle that enables you to change the area the movie will zoom into.


How to change the Zoom-Pan effect


When you add a Zoom-Pan effect, this changes the view for all frames that follow it in the movie. Select any frame after the effect, with Apply Effects set to on, and you'll see the green rectangle that indicates the displayed area of the movie.


Changing the position or size of the green rectangle in any frame changes the view for all frames affected by that Zoom-Pan effect - you don't need to find the frame where you originally added the effect in order to change it.


How to delete a zoom-pan effect

1. Find the Zoom-Pan effect in the framebar. The easy way to do this is by selecting the effect in the Jump To control on the toolbars, to jump straight to its frame. You should see something like this in the framebar:




The  icon indicates the start frame of the transition - where the Zoom-Pan starts.


The  icon indicates the end frame of the transition - where the Zoom-Pan ends.


2. Right click the  icon and select "Delete Zoom/Pan" or Click the Delete Zoom-Pan button in the toolbar.

Changing the transition speed for a Zoom-Pan effect

Find the Zoom-Pan effect in the framebar. The easy way to do this is by selecting the effect in the Jump To control on the toolbars, to jump straight to its frame. You should see something like this in the framebar:




The  icon indicates the start frame of the transition - where the Zoom-Pan starts.

The  icon indicates the end frame of the transition - where the Zoom-Pan ends.

- Drag either the icons in the framebar to move the start and end of the transition.

or

- Double click the  icon to see the Zoom-Pan effect properties window.

How to zoom back out

When you add a Zoom-Pan effect, this changes the view for all subsequent frames in the movie. If you zoom in, then want to zoom back out later, to show the entire movie, you need to add a second Zoom-Pan effect.

To zoom back out and show the entire movie

1. Find the frame where you want to zoom out.
2. Click the Add Zoom-Pan button on the toolbar.
3. On the Zoom-Pan properties window, select "Entire movie" for the Show Area setting.
4. Click OK.

The movie will zoom back out at that point.

Cropping and Autoscrolling

After recording a movie, you may only wish to show a part of the recorded area in the final movie. Use BB FlashBack's cropping function to cut down the movie to a smaller area and have it automatically scroll to keep the mouse in view.

How to crop a movie

Open the movie in BB FlashBack Player and click the cropping button to turn cropping 'on'. Or, select "Set Cropping Rectangle" from the Effects menu.

You will see a blue rectangle that indicates the size the movie will be cropped down to. Resize and position it as required.

To turn cropping off, click the cropping button again.

How to preview the cropped movie

Click the Apply Effects button on the toolbar, or select the "Apply Effects" item from the Effects menu.

Note: the Apply Effects function also applies any Zoom-Pan effects you've added - it shows exactly what you will get when you export the movie (apart from any scaling or other effects you add at export time).

Autoscrolling Cropped Movies

The crop rectangle can follow the mouse to keep it in view. Use options in the Effects -> Autoscroll Cropping Rectangle menu to have the mouse either in the centre or near the centre of the movie.

When autoscrolling is set on the cropping rectangle, any ZoomPan effects you add can only be resized, not moved, because they will also be automatically positioned to keep the mouse in view.

Making Cropping Permanent

To decrease the size of the FlashBack movie file (.FBR file) you can make cropping 'permanent', effectively throwing away everything outside of the cropping area.

To do this: on the Effects menu, select "Make Cropping Permanent".

The Mouse Cursor

Highlighting the mouse cursor

By default, BB FlashBack draws a yellow highlight circle around the mouse cursor. If you want to change the colour, opacity, size and outlining of this circle, or not show it at all, use the *Highlight Cursor* option in the *Effects* menu.

Note: if you use the 'cursor trails' option in Windows, the highlight circle will not be visible.

Smoothing mouse movements

BB FlashBack enables you to smooth out the mouse movements in selected frames.

The mouse will move smoothly from its position in the first frame of the selection to its position in the last frame of the selection, stopping to make any clicks it needs to along the way.

Use this feature to remove any distracting jumps in mouse movements.

How to smooth mouse movements in a section of the movie

1. Select the frames in which you want to smooth out the mouse movements. BB FlashBack will make the mouse move smoothly from the position in the first frame of the selection to its position in the last frame of the selection.
2. Select the 'Smooth cursor movements' item from the Actions -> Cursor menu.

Hiding the mouse cursor

BB FlashBack can hide the mouse cursor during playback. You can select a series of frames and choose to hide the cursor in those frames when the movie is played back.

How to hide the mouse cursor

1. Select the frames in which you want to hide the mouse.
2. In the Actions menu, select Mouse Cursor -> Hide the mouse cursor.

The selected frames will be drawn in blue in the frame bar, indicating that the mouse is hidden in those frames.

To un-hide the cursor in those frames just select the frame and select *Actions -> Mouse Cursor -> Show the mouse cursor*.

Mouse action animations

When a mouse button is pressed during recording, BB FlashBack can show an animation in the final movie, to indicate the action that occurred. These animations can be customised by editing the bitmaps used to create them.

How to switch mouse action animations on and off

In the Effects menu, select Highlight Cursor. Then select or deselect the "Highlight mouse clicks" setting.

How to use the default animations instead of customised animations saved in a movie file

If you play back an FBR file with customised mouse animations but want to use the default animations or your own customised images, select the *Reset mouse action images* item from the *Edit* menu in BB FlashBack Player.

How to customise mouse action animations

The images used in animations are contained in the "custom" folder, which is in the BB FlashBack install folder. When Player starts, it loads these images. Take a look in this folder and you will see a number of .PNG image files called LeftMouseDown1.png, LeftMouseDown2.png etc.

When a mouse action occurs in the movie, BB FlashBack overlays these images onto the mouse cursor in a sequence to create the animation. For example, if the right mouse button was pushed down, it would overlay RightMouseDown1.png, then RightMouseDown2.png, then RightMouseDown3.png to create the animation effect.

To change the animation seen for a mouse action, you simply need to change the image files used.

When you change the animations, your customised version is saved into the movie (FBR) file and also included in all exports you make.

For example: if you wanted to change the right mouse down animation, you could edit the 3 files called RightMouseDown1.png, RightMouseDown2.png and RightMouseDown3.png in an image editor application to create a completely different effect. Each of the images must be the same size.

Supported formats for the image files are: BMP, GIF, PNG, JPG, JPEG and ICO.

If you wanted to use BMP files instead of PNG files for the right mouse down animation, you would remove the RightMouseDown<frame number>.PNG files from the *Custom* folder and replace them with RightMouseDown<frame number>.BMP files.

The actions available for animation are:

- Left button down
- Left button up
- Left button double click
- Right button down
- Right button up
- Right button double click
- Middle button down
- Middle button up
- Middle button double click
- Scroll wheel up
- Scroll wheel down

No default animation is supplied for middle button actions.

Transparency

The animation images need transparency, or they would completely obscure the mouse pointer and the movie around it. BB FlashBack handles transparency in the images in one of two ways:

- By treating one colour in the image as 'transparent'. The transparent colour is set by the TransparentColour variable in the custom.cfg file - see the section More advanced customisation below. If you use normal BMP, GIF, JPG or 8 bit PNG images you must use this method and specify a colour as 'transparent'.
- By using transparency information encoded into the image. This is only available for 32bit 'ARGB' BMP files and 24bit PNG format images. 24bit PNG images can be saved by Adobe Photoshop and other image processing applications.

More advanced customisation

In the custom folder is another file, custom.cfg that holds details on how Player will use the animation images. It is a text file and you can edit this to change the number of frames of animation, speed of animation and the transparent colour in the image files. The file holds a number of numeric values that relate to the various mouse action animations.

You can change these values to change the animation.

Here is a sample set of lines from custom.cfg that control the left button down animation. Comments on how you could change the value are on the right.

LeftMouseDownDoDraw=1	Change this value to 0 to not include this particular animation (left button down) in the movie - no animation will be displayed.
LeftMouseDownImagesCount=3	Change this to add more frames of animation or have less. Remember, if you changed this value to 4, for example, you would need to add an extra image file: LeftMouseDown4.bmp
LeftMouseDownDuration=500	The time in milliseconds that each frame of the animation is displayed for.
LeftMouseDownOffsetFromCursorHotspotX=-12	These two values specify the position of the 'hotspot' in the image - the position of the end of the cursor. To locate the animation exactly over the end of the mouse cursor, you may need to change these values.
LeftMouseDownOffsetFromCursorHotspotY=-12	
LeftMouseDownTransparentColor=0x00FF00FF	The colour in the image that will be made transparent when it is overlaid on top of the movie.

Putting the mouse in front or behind other objects

By default the mouse cursor will move behind other objects, like textboxes, images and highlights, which you add to the movie. You may want the mouse cursor to move in front of them, so they appear to be part of the original recording. BB FlashBack allows you to do this.

Note: the exception to this is the webcam video window - this always appears in front of the cursor and other objects added in BB FlashBack.

How to make the cursor move in front of other presentation objects

Select the 'Bring cursor to front' item from the *Actions -> Cursor* menu. If you wanted to send the cursor behind other objects, you would select the 'Send cursor to back' item from the same menu.

Re-recording the mouse cursor

There may be occasions when you want to tidy up or correct mouse movements in the movie. BB FlashBack allows you to do this by letting you re-record the mouse for part or all of the movie.

How to re-record the mouse for a section of the movie

1. Select the frames in which you want to re-record the mouse
2. Select the menu item *Actions -> Cursor -> Re-record mouse cursor -> At selected frames*. A countdown will be displayed, to allow you to get the mouse into the correct starting position. When the count down finishes, the movie will play
3. Move the mouse as you wish it to be seen in the final movie and BB FlashBack will record the movements

To re-record the mouse for the entire movie, just select the *Actions -> Cursor -> Re-record mouse cursor -> For whole movie* menu item.

Removing inactive sections

BB FlashBack allows you to select or delete sections of the movie where there is nothing of interest happening.

Defining Inactivity

First you need to define what is regarded as an 'inactive' section.

Go to *Actions -> Select Inactivity -> Define Inactivity*. On this window you can define 'inactivity' as the absence of annotations, mouse movement or key presses, and how long the absence needs to last before it is regarded as 'inactivity'.

Selecting Inactivity

Use the *Select Next Inactive Section* and *Select Previous Inactive Section* menu items in the *Actions -> Select Inactivity* menu (or use the shortcut keys: Ctrl-N and Ctrl-P) to select the next or previous inactive sections from the current frame.

Deleting Inactivity

Use the *Delete all Inactive Sections* menu item on the *Actions -> Select Inactivity* menu to delete all inactive sections from the movie.

Using Markers in movies

BB FlashBack places no limits on the size of the movies you can create. Though practically you are restricted by the amount of free disk space available to your PC, you can easily create movies that span many minutes, possibly hours.

If there are particular events in a large movie that you need to be able to view again and again, finding them could prove to be a tiresome operation.

To enable fast access to different points in a movie, BB FlashBack Player lets you add markers. Markers are simply a way of labelling a particular frame, so that you can easily find it later.

How to add or delete a marker

Markers are added with the *Marker* item on the *Insert* menu. They are deleted by either:

- Going to the Markers -> Delete sub menu from the Edit menu, and selecting the marker you wish to delete.

or

- In the framebar, right clicking on the frame containing the marker and selecting Delete Marker.

How to move to a marker or see the list of markers

The top items in the *Edit* -> *Marker* sub menu are a list of the markers in the current movie. Selecting one of these will jump straight to the frame that contains the marker.

You can also see the markers listed in the *Jump To* dropdown list in the Player toolbar. When viewing the movie in the Player you can move forwards or backwards through marked frames by using the *Next marker* and *Prev marker* items on the *Movie* menu.

Inserting video files

BB FlashBack can insert a video file into a screen recording. Note: this may greatly increase the size of the FBR file.

How to insert a video file into a Flash Back movie

1. On the main menu, select Insert then 'Video File'
2. Select a video file.
3. Select how it will be sized to the FlashBack movie.
4. Set the 'in' and 'out' transitions (see this page for more about Transitions)

Note: BB FlashBack may not be able to insert some video files. In general, if Windows Media Player can play it, BB FlashBack should be able to add it to your movie.

Pauses

You can pause the movie at any frame by adding a Pause object. A Pause object will pause playback for a set period of time or until the mouse is clicked. Sounds do not play while the movie is paused.

How to add a pause object

1. Select the frame you want to add the pause to.
2. In the Insert menu, select Pause .

How to change the settings of a Pause Object

Double click the pause object icon in the framebar to show its settings window.

Pausing while a textbox, image or other object is displayed

In the 'Duration' settings for a textbox, image or other in-movie object, you can set the movie to pause while the object is displayed. This will create a pause object in the same frame as the in-movie object. You can set the duration of this pause either from the 'Duration' settings of the in-movie object it was created by, or by double clicking the pause object icon in the framebar.

Note: Other objects that start in the same frame will be unable to set their duration - they will take the same duration as the object with the linked pause object.

Displaying a 'Click to continue' image while the movie is paused

If you select the 'Pause until mouse clicked' option for the pause, you can also select the "Show 'paused' graphic while movie is paused". The default pause graphic appears in the top left corner of the movie and says "Paused: click to continue". See the help below if you want to change the appearance or position of the pause graphic.

How to change the pause graphic

1. On the Player main menu select Pause Graphic -> Set Pause Graphics from the Edit menu.
2. Select a bitmap file.

The selected bitmap will now appear when the movie reaches an inserted pause.

To revert back to the default pause image, select Pause Graphic -> Set Default Pause Graphics from the Edit menu.

How to change the position of the pause graphic

1. On the Player main menu select Pause Graphic -> Set Pause Graphics Position from the Edit menu.
The pause graphic will appear in the movie area.
2. Use the mouse cursor to position the pause graphic.
3. When you are satisfied with its position, leave it and carry on with any other editing operations.

The pause graphic will appear in the position you selected, when the movie reaches an inserted pause.

Start and End Titles

You can add 'Titles' to the start and end of a movie. Titles are text and/or an image on top of a plain colour background.

Note: When BB FlashBack adds titles, it adds a number of highlight, textbox, pause and image objects to the start or end of the movie. You can edit these objects manually to change the text or image position, but for altering the duration of the titles, it is simpler to use the 'Start/End Titles' window.

How to add Titles

1. Select 'Start/End Titles' on the Effects menu or click the button on the toolbar.
2. Set the Title properties - give it some text and/or an image.

Changing the Titles Appearance

To change the position of the text or image

When BB FlashBack adds titles with text and images, it creates the text or image by adding a standard textbox or image object to the movie. You will see these at the start or end of the movie.

Change the position of the text or image by clicking and dragging the textbox or image object, as you normally would.

To change the size of the image

See the help for 'To change the position of the text or image'. Change the size of the image object added by BB FlashBack when it created the titles.

To change anything else

Select 'Start/End Titles' from the Effects menu or click the button on the toolbar and change the title properties.

You can always alter the titles by editing the image, textbox, pause and highlight objects added by BB FlashBack to the start or end of the movie. However, for things like altering the duration of the movie, it is much easier to use the Titles properties window.

Displaying invisible keystrokes

Some keypresses, such as function keys or the Insert, Delete, Home and End keys, often do not produce visible output. If you want the user to know when these 'invisible' keys are being pressed, BB FlashBack can automatically create textboxes to show them.

How to show invisible keystrokes

1. Select 'Show Invisible Keystrokes' from the Effects -> Display Invisible Keystrokes menu.
2. Set properties for the textboxes that will show the keystrokes.

This will create textboxes to show any invisible keystrokes in the movie. You can edit the textboxes as normal in BB FlashBack Player.

To hide invisible keystrokes, select 'Hide Invisible Keystrokes' from the Effects -> Display Invisible Keystrokes menu. This will delete all textboxes created by 'Show Invisible Keystrokes'.

Transitions

BB FlashBack can add 'transition' effects to a movie to provide a more visually appealing transition from one part of a movie to the next. They can be added automatically when inserting a video file or FlashBack movie to cover the 'joins' at the start and end of the inserted movie.


When you insert a transition at a frame, it creates a transition between that frame and the frame before it.

You can set the type of transition, its duration and whether it pauses in the middle. The 3 types of transition are:

1. Fade to white - if you add the transition at frame 100, for example, frame 99 will fade to white and frame 100 will fade in from white.
2. Fade to black - again, frame 99 fades to black and frame 100 fades in from black.
3. Cross-fade - this fades frame 99 into frame 100.


Transitions can be added automatically when you insert a video file or FlashBack movie into your movie.

How to add a Transition

1. Find the frame in the movie that contains the 'join' you want to have transition smoothly.
2. Select the *Transition* menu item in the Insert menu or click  the button on the toolbar.
3. Set the Transition properties

Transition Frames

When you add a Transition, it looks like this on the framebar:



The grey frames are part of the Transition and cannot be edited like normal frames. They cannot be deleted without deleting the Transition. You cannot insert objects in these frames or perform other editing operations on them.

Exporting Movies

If you want non-FlashBack users to see a movie you've created, you'll need to export it.

File Formats

Here are the file formats BB FlashBack can export to:

Flash

Easiest format to embed in a web page. Includes full playback controls. A very high (>95%) of PC and Mac users should be able to view movies in this format. Flash and EXE formats are the only formats that support interactive elements like 'click to continue' textboxes and buttons.

To learn more, see [Exporting to Flash](#).

QuickTime (H264)

QuickTime uses advanced compression to achieve a good balance of quality and file size. QuickTime movies can be embedded in web pages and streamed to viewers. They will play back in all Mac's but only PCs that have QuickTime or iTunes installed. You need QuickTime 7 or later installed to export to QuickTime format.

To learn more, see [Exporting to Quicktime \(H264\)](#).

Windows Media Video (WMV)

As with QuickTime, you can achieve good quality and file size with this format, and WMV movies can be embedded in web pages. WMV files should play back on virtually all PCs, but generally not on Macs. You need Windows Media Player 9 or newer to export to WMV format.

To learn more, see [Exporting to Windoes Media Video](#).

MPEG4

This format can also achieve low filesize with good quality, though it will probably not compress video as well as QuickTime and WMV. By default, Windows Media Player can not play back MPEG4 format video files, so this format may not be a good choice if you will distribute the video to Windows PCs. However, the format is supported by Apple Mac OS X and the iPhone, iPad and video capable iPods.

To learn more, see [Exporting to MPEG4](#).

Standalone EXE

BB FlashBack can export your movie as an executable file (EXE file) that plays the movie when opened. It has configurable playback controls, 'lossless' quality images and can achieve very small file size. The EXE file will only play back on Windows PCs. EXE and Flash formats are the only formats that support interactive elements like 'click to continue' textboxes and buttons.

To learn more, see [Exporting to Standalone EXE](#).

AVI

A very popular file format for displaying movies. However, exporting to AVI can be complicated for less technical users, because you need to pick a *codec* to encode the movie. The image quality and file size is very dependent on the codec used. If a PC doesn't have the codec you used to encode it, it may not be able to play back the AVI file, and the codecs you can guarantee are installed on all Windows PCs may not give good results.

To learn more, see Exporting to AVI.

MS PowerPoint (PPT)

BB FlashBack can save you movie as a PowerPoint file, with the movie embedded in the first slide. You need MS Office 2000 or newer, including PowerPoint, to export to this format.

To learn more, see Exporting to MS PowerPoint.

GIF

This format is an animated image file, so it very easy to embed into webpages. However, it is only suitable for smaller animations, with a low frame rate and short duration. When embedded in a webpage, it can be played back by all devices and browsers. To learn more, see Exporting to GIF.

To learn more, see Exporting to GIF.

I want to send it to other BB FlashBack, BB FlashBack Express or BB TestAssistant users

Just send them the FlashBack Movie file (FBR file) created by BB FlashBack - they will be able to play it, and the FlashBack file is often smaller than other formats.

I want to display the movie on a webpage

Flash, QuickTime and WMV formats can all be embedded on webpages.

I want to include the movie on a CD

Try exporting to Flash, QuickTime, WMV and EXE formats. The format that gives best image quality at lowest file size may depend on the content of your movie. EXE format often gives smallest file sizes if 'normal' Windows applications are recorded.

If your movie contains moving video or lots of photographic images, Flash, QuickTime and WMV formats may produce smaller exports.

Comparison of Export formats

	AVI	WMV	QuickTime	EXE	MPEG4	GIF	Flash-SWF	Flash-FLV
Quality	Depends on codec (Read more)	High	High	Lossless	High	Low	Lossless or JPG	High
Filesize	Depends on codec (Read more)	Good	Good	Depends on recording*	Good	Can be very large	Depends on recording*	Good
Can contain interactive elements				✓			✓	✓
Embed in Webpage		✓	✓			✓	✓	✓
Compatible on a wide range of PCs	Depends on codec (Read more)	✓	Requires QuickTime or 3rd party software to be installed	✓	Requires QuickTime or 3rd party software to be installed	✓ (when embedded in a webpage)	✓	✓
Compatible with Macs	Depends on codec (Read more)	Not playable by Macs without 3rd party software	✓		✓	✓ (when embedded in a webpage)	✓	✓

The filesize of EXE and Flash-SWF exports may be significantly higher than AVI, WMV, QuickTime or Flash-FLV if the movie contains movement or animation.

Exporting to Flash Format

Flash is a file format commonly used to display movies and animations.

Because Flash movies can easily be viewed on most modern Internet browsers, it is a good format to use when distributing movies to PC or Macintosh users that do not have the BB FlashBack installed.

Flash exports can contain interactive elements like 'click to continue' textboxes and buttons. They can be embedded into web pages, and contain playback controls.

How to export a movie to Flash format

On the Player main menu, select the *Export to Flash* item on the *File* menu. Or, on the *File* toolbar, click the *Export* button and select the Flash format. For more help see Flash export options [162].

FLV and SWF formats

BB FlashBack can export the movie as either SWF or Flash Video (FLV) formats. Each have their advantages and disadvantages. See Selecting between Flash Video (FLV) and Standard Flash (SWF) [164] for details.

Files generated by Flash exports

Depending on the options selected, BB FlashBack generates a different bunch of files to create your Flash export. It can generate a single SWF file, multiple SWF files or an SWF and FLV file. See Files generated by Flash exports [167] for more help.

Quality and file size of Flash exports

There are a number of settings you can use to balance file size vs quality.

See Adjusting the quality and file size of Flash exports [165] for more help.

Custom Flash playback controls

If you have Flash authoring skills, you can create your own playback controls and have BB FlashBack use them during export, so they are included in the exported movie. See Customising the Flash playback controls [166] for more help.

Restricting third-party use of Flash exports

BB FlashBack allows you to restrict how your Flash exports are linked to or embedded by 3rd party websites. See Restricting third-party use of Flash exports [171] for more help.

Flash export options

General Tab

- Export Frames - use these controls to export either the entire movie or just a set of frames. If you selected a set of frames before exporting, this set will be shown in the 'Selected frames' controls.
- Frame rate - a higher frame rate means smoother movement in the movie, but usually increases file size.

- Scaling - use the controls to reduce the dimensions of the Flash movie.

Playback Tab

- Starting playback - you can decide whether the movie should start to download and play automatically, when the webpage it is embedded in is opened, or whether it should wait until it is clicked.
- At movie end - set whether playback should loop continuously back to the start when it reaches the end.
- Preview Image - An image of the first frame of the movie can be displayed before the movie is downloaded. Optionally, this preview image can be in a separate SWF file named "<moviename>_preview.swf", to make it easier for you to customise the preview image - this is set on the SWF File Generation tab.
- Pausing playback - the movie can be set to pause and restart when it is clicked, and also show a 'paused' overlay on the movie while it is paused.
- Preload - Flash movies exported by BB FlashBack and put on webpages will 'stream' to the end-user. This means that the movie can start playback in their web browser before it has completely downloaded to the user's PC. Playback starts when enough has been downloaded to allow the movie to play to the end without stopping to wait for more to be streamed down.
- Setting a value for Preload overrides this default behaviour. It starts playback when a preset % of the movie has been downloaded.

Video Quality Tab

Select Flash Video (FLV) or Standard Flash (SWF). See [Selecting between Flash Video \(FLV\) and Standard Flash \(SWF\)](#) for more help [164].

Depending on whether you select FLV or SWF, there will be different controls to help you adjust the file size and quality of the export. See [Adjusting the quality and file size of Flash exports](#) for more help [165].

Audio Tab

See [Sound export options](#) for more help.

Playback Controls Tab

To improve the viewing experience for your audience, BB FlashBack can add playback controls to exported Flash movies. This allows the viewer to pause, rewind, adjust the volume and navigate to different areas of the movie with a media player-type interface.

You can select one of the pre-defined playback control bars that come with BB FlashBack, and decide which controls to include on the toolbar.

If you have SWF authoring software and a good knowledge of Flash, you may want to see [Custom Flash playback controls](#) [166] for information on how to use your own playback controls.

HTML Templates Tab

When exporting to Flash, BB FlashBack creates an HTML file that you should open to view the Flash movie. It has the same name as the Flash (SWF) file.

If you want to change the default HTML generated, BB FlashBack lets you create HTML templates to enable this.

See How Flash exports use HTML files [166] for more help.

SWF File Generation Tab

When exporting as an SWF file, you can either have the movie and playback controls in the same SWF, or separate SWFs.

Having them in the same SWF means the movie is easier to embed in documents such as a PDF file. Having them in separate files means you can have 'download on demand' type functionality where you embed the movie in a webpage, but the movie only downloads when it is clicked.

See Files generated by Flash exports [167] for more help.

More Tab

- Show or Hide the mouse cursor
- Colour format - for some movies, reducing the number of colours can result in a file size reduction.
- Preload - you can set how much of the Flash movie should be downloaded before playback starts automatically. The default is to have the movie only start when it calculates that playback will be able to proceed to the end if the current download rate is maintained.

Security Tab

BB FlashBack can set Flash exports to expire at a certain date or require a password for viewing. These options only work for exports to a single SWF file.

There are also options to prevent the exported Flash movie from being embedded in third party webpages. See Restricting third-party use of Flash exports [171].

Selecting between Flash Video (FLV) and Standard Flash (SWF)

There are two basic types of Flash export: Flash Video (FLV) and Standard Flash (SWF). The best one to select will depend on the movie you are exporting.

How to select Flash Video (FLV) or Standard Flash (SWF)

Select the *Video Quality* tab on the Flash Export Options window, and then select the export type.

Advantages of FLV

- Handles moving video better. FLV should create a smaller file than SWF if your movie contains moving video. Also, moving objects will not leave 'trails' behind them, which can be the case with SWF movies.
- Has no restriction on length. SWF has a limit on the number of frames it can contain in one movie. BB FlashBack will automatically reduce the frame rate when exporting to SWF if your movie would exceed this limit, but FLV may be a better choice for longer movies.

Advantages of SWF

SWF can be easier to embed in webpages, PDF files and other documents.

When BB FlashBack exports in FLV format, it creates two separate files that contain the movie and the playback controls: <moviename>_toolbar.swf and <moviename>.flv (where <moviename> is the name of the .FBR file open in BB FlashBack).

If you need to embed the movie in a PDF file, an MS Office document, or embed it into a webpage using an HTML editor like DreamWeaver, you need the movie to be all in a single file. BB FlashBack can create a single SWF file that contains the movie and playback controls.

See Files generated by Flash exports [167] for more help.

Restrictions on the dimensions of FLV Movies

The height and width of FLV movies will always be a multiple of 16. It is a characteristic of the FLV format that it performs best when movies are sized in this way.

This means that if FLV is selected, the Flash movie you export may have padding on the left and right, and either the top or bottom (depending on where you choose to have the playback controls positioned) to make the width and height multiples of 16.

You can select the colour of this padding to match the webpage the movie will be embedded in.

Adjusting the quality and file size of Flash exports

BB FlashBack includes a number of options to let you adjust the file size and quality of your final Flash export.

The video quality options you can access depend on whether you select Flash Video (FLV) or Standard Flash (SWF) on the Video Quality tab of the Flash Export options dialog. See Selecting between Flash Video (FLV) and Standard Flash (SWF) [164] for details.

Video Quality Settings for Flash Video (FLV)

- FLV Type - H263 should give smaller files, particularly if your movie has moving video. 'ScreenVideo' encoding has been developed specifically for screen recordings. It will export larger FLV files than H263, but very high quality.
- Quality - Higher quality values mean better image quality, but larger file sizes.
- Bitrate - Higher bitrate means higher quality but larger file sizes. The encoder will try to attain the quality you set at the bitrate specified, but if the quality is higher than can be achieved at the specified bitrate, it will increase the bitrate to reach the quality. I.e. quality takes priority over bitrate.
- KeyFrames - More keyframes usually mean better quality, but larger file sizes.

Video Quality Settings for Standard Flash (SWF)

- Compression - Select JPEG or Lossless compression. JPEG should give smaller file sizes, particularly if the movie contains photo type images. However, moving objects can leave 'trails' or artefacts behind them due to the nature of JPEG compression. Lossless gives lossless quality images and no 'trails' behind moving objects, but larger file sizes.

- **Quality** - A higher quality setting means better image quality, but larger file sizes.
- **Optimise Compression** - This is an option on JPEG compression. When selected, this analyses all images in the movie and applies high quality, lossless, compression to images in the movie that compress well with this technique. Turning this option off may reduce filesize a little for movies that have lots of photo-type images.
- **Frame Rate** - Higher frame rates usually mean smoother movement, but also larger SWF and FLV files. Change the frame rate on the General tab of the Flash export options window.

Audio Settings

If your movie contains audio, changing audio settings may result in large changes in the exported file size.

Go to the *Audio* tab of the Flash Export Options window to set audio options.

- **Format** - If you select a custom format: higher Khz values mean better quality, 16 bit is higher quality than 8 bit. Higher quality means larger files, as usual. Stereo produces larger files than mono.
- **MP3 Compression** - By default BB FlashBack uses MP3 compression to reduce the file size, but there are a number of quality settings you can select. As usual, the higher the quality, the larger the file.

Colour Depth

For some files, typically those that contain few or no photo type images, limiting the number of colours in the exported movie can reduce the size of the file.

How to change the colour depth of the exported movie

1. Go to the 'More' tab in the Flash export options window.
2. Select a colour depth from the 'Colour depth' drop down list, export the movie and see whether this results in a reduced file size.

Customising the Flash playback controls

BB FlashBack is installed with 3 different styles of playback controls. If you want a different look or added functionality and have Flash authoring skills, you can specify an SWF to use in place of the supplied templates on the Playback Controls tab of the Flash Export options window.

BB FlashBack is installed with .FLA source files, .AS ActionScript files and .FLP project files for the 3 included playback control templates, in an "SWFControlBars" folder in the application install folder. These files should be modified to produce the customisations you need.

For each of the three templates, there are 3 FLA and SWF files. e.g. for the 'metallic' template:

- DefaultControlBar.fla / .swf - multiple SWF export (toolbar and movie in separate SWF files), or FLV export. Uses ActionScript 2.
- DefaultControlBarSingle.fla / .swf - single SWF export (playback controls and movie in the same SWF file), ActionScript 2
- DefaultControlBar3.fla / .swf - FLV export, when the movie contains interactive objects like 'click to continue' textboxes. Uses ActionScript 3.

How Flash exports use HTML files

When BB FlashBack exports to Flash it generates an HTML file that embeds and displays the Flash movie. This HTML file demonstrates how to embed the movie in a webpage. This HTML file has the same name as the SWF file.

Changing the default HTML

The default HTML file is very simple - it just shows the movie against a white background. You may want to add more to this page, displaying a company logo or description of the movie, for example. You can just edit the HTML file created by the export, but if you want to export the changed HTML many times, it may be easier to make a new *Template*.

How to add a new HTML template

1. Go to the 'HTML Template' tab on the Flash export options dialog.
2. Select the 'New' button and give the new template a name.
3. Click the 'Edit' button to enable the HTML to be edited, or click the 'Select' button to select an HTML file you have already prepared.
4. The HTML can be edited in the dialog. In the exported HTML, the <SWFObject> tag will be replaced by code that displays the Flash movie.
5. Click 'Save' when the HTML has been changed to your satisfaction.

You can select the new template via the 'Template name' combo box at the top of the 'HTML Template' tab and this HTML will be used in the export.

See also Displaying a Flash export on a webpage [168].

Files generated by Flash exports

BB FlashBack generates different files depending on whether you selected SWF or FLV format, and, for SWF format, whether you want to enable download-on-demand or embedding in PDF and other documents.

If you want to embed the movie in a PDF file, MS Office document or are having trouble embedding it in a webpage using DreamWeaver or similar HTML editors, you need to export the movie as a single SWF file - see details below.

An HTML file that embeds the movie is always generated, regardless of the format selected and other settings.

FLV Format

Generated files:

- <movienam>.html - demonstrating how to embed and display the movie in a webpage.
- <movienam>.flv - the movie
- <movienam>_toolbar.swf - the playback controls. This is the file that needs to be embedded in a webpage or other document to display the movie. It loads the FLV file.

SWF Format

There are two options.

- A single SWF that contains the playback controls and the movie. This means you can embed the movie in PDFs and MS Office docs, and can make embedding it in a webpage easier, if you use an HTML editor like DreamWeaver.
- Multiple SWFs, where the playback controls and movie are in separate SWF files. The advantage of this approach is that the movie can download on-demand - it sits in the webpage/document showing a preview image and a 'play' icon and only downloads the full movie when clicked. Otherwise, if you choose to have a single SWF, the entire movie downloads when the webpage is loaded.

You can select to export single or multiple SWF files on the SWF File Generation tab in the Flash Export Options window.

Files generated when 'Single SWF' is selected:

- <moviename>.html - demonstrating how to embed and display the movie in a webpage.
- <moviename>.swf - contains the playback controls and movie. Files generated when 'Multiple SWFs' is selected:
- <moviename>.html - demonstrating how to embed and display the movie in a webpage.
- <moviename>.swf - the movie
- <moviename>_toolbar.swf - the playback controls. This is the file that needs to be embedded in a webpage or other document to display the movie. It loads the <moviename>.swf file. and optionally
- <moviename>_preview.swf - this is generated if you have the 'do not download until clicked' option selected on the Playback tab, and selected to have a preview image, and selected 'use separate swf file' on the SWF File Generation tab. Otherwise the preview image is inside the _toolbar.swf file.

Flash Player Version Compatibility

- If you export as FLV Flash Player v7 and above is required to view the movie.
- If you export as SWF Flash Player v6 and above is required.

Displaying a Flash export on a webpage

When BB FlashBack exports to Flash format, it creates a webpage (HTML file) that has the movie embedded in it.

Embedding the movie in your own webpage requires only a couple of steps - you need to copy/upload the exported files up to your webserver and add HTML code to your webpages that refers to the SWF file that displays the movie.

BB FlashBack generates the HTML code you need for embedding when it does the export.

For example: I export a movie called mymovie.fbr to Flash, selecting to export as SWF, not FLV. Two files are generated:

- mymovie.html

- mymovie.swf

Open mymovie.html. Under the movie are instructions on embedding the movie in a webpage. Copy the code in the entry field to the clipboard and paste it into your webpage where you want the movie to appear. If your webpage and all the exported SWF and FLV files that you uploaded are in the same folder, the code should work ok and display the movie.

If your webpage and the uploaded files are in different folders you will need to change the code so it refers to the files. Look through the code you copied to your page. In two places it will refer to a .swf file ("mymovie.swf" or "mymovie_toolbar.swf"). In each of these places you will need to add a folder path so it refers to the correct location of the toolbar swf file.

See also: Files generated by Flash exports [167]

Having the movie and toolbar files in separate folders

If you export a movie and the toolbar as two separate files, it is possible to save the movie into a folder different from where the toolbar is located. To achieve that, open the *SWF File Generation* tab, find a setting named *Specify path to movie file* and check it. In the *URL of movie file* text field, enter a path to the movie file; it can be either a relative path or a URL.

If you didn't export the movie as above but now want to put it into a separate location, you can use Flashvars [169]. You will need to add the **fileName** parameter into generated HTML code.

Changing the controls text (and other movie settings) via HTML and Flashvars

You can override all text strings in the playback controls by specifying Flashvars in the HTML that embeds the Flash movie. You can also override many of the export settings in this manner.

For more information on how to use Flashvars, see this article: http://kb2.adobe.com/cps/164/tn_16417.html

Supported Flashvars

- str1 (string) - an escaped string with the text of the first item in the "FlashBack Logo" button dropdown. For example: Created%20with%20BB%20FlashBack
- str2 (string) - an escaped string with the text of the menu item on "FlashBack Logo" button dropdown that opens the BB FlashBack homepage. For example: Visit%20www.bbflashback.com
- str3 (string) - an escaped string containing text to be shown to the right of the 'Hide toolbar' toggle control. For example: "Hide"
- str4 (string) - the URL that is opened by the link on the "FlashBack Logo" dropdown
- str5 (string) - text that appears if the user's Flash player version is not high enough to play the movie. By default, this is Flash "Player v9 or above required. Update your player here:"
- showToolbar ('true' or 'false') - sets toolbar visibility
- topToolbar ('true' or 'false') - sets toolbar location, bottom for false, top for true
- showFullScreen ('true' or 'false') - sets visibility of the full screen button
- notScaleInFullScreen ('true' or 'false') - sets whether the movie is scaled in the full screen mode

- autoHide ('true' or 'false') - if set to true, the toolbar will automatically hide itself
- showAutoHide ('true' or 'false') - sets visibility of the auto hide button
- showTimer ('true' or 'false') - sets visibility of the time elapsed / duration display
- showTimeline ('true' or 'false') - sets visibility of the timeline
- showNextButton ('true' or 'false') - sets visibility of the next frame button. This parameter is ignored in the case of FLV movies
- showPrevButton ('true' or 'false') - sets visibility of the previous frame button. This parameter is ignored in the case of FLV movies
- showFBLogo ('true' or 'false') - sets visibility of the BB FlashBack logo button that shows a dropdown menu with a link to the BB FlashBack website
- showVolumeBar ('true' or 'false') - sets visibility of the volume button
- fileName (string) - the file name of the movie that must be displayed and controlled by the toolbar SWF. For example: test.swf or test.flv
- showPausedOverlay ('true' or 'false') - indicates whether user has chosen to have the Pause symbol shown when the movie is paused
- pauseByClickingOnMovie ('true' or 'false') - indicates whether the user has chosen to allow the movie to be paused or played when a user clicks on the movie
- startingPlaybackMode (integer) - indicates the playback mode chosen by the user. Values are:
 - 0: Only download and play the movie when the 'Play' overlay button is clicked
 - 1: Automatically download the movie but do not play until it is clicked
 - 2: Automatically download and play the movie
- preloadPercent (integer, 0-100) - the percent of the movie that should be loaded before playback starts. The default of zero means that playback should start 'automatically' - when it is calculated, based on the current download rate and duration of the movie, that playback should be able to start and complete without pausing to wait for further downloading.
- previewFilename (string) - if this is non-null, it is the name of the 'preview image' SWF that should be loaded and shown before the main movie is downloaded and played.
- previewMode (integer) - indicates how a preview image will be used. Values are:
 - 0: no preview image
 - 1: Load preview image from an external SWF file. The name of the file will be passed in the previewFileName parameter.
- scaleMode - give this a value of 'noscale' if the movie should not scale when in fullscreen mode.
- dimPreview ('true' or 'false') - set to 'true' to have a darker preview image. Default = 'false'.
- urlParams ('true' or 'false') - set to 'true' to let the SWF file read information from URL parameters as described below.

Using URL parameters to jump to a frame in the movie (and change other settings)

Instead of specifying Flashvars in HTML, you can pass parameters listed above directly in URLs, for example: `http://mydomain.com/path/movie.html?startingPlaybackMode=0`

Note: Values of URL parameters override values of Flashvars with the same names, if the latter are present.

In addition, when changing settings in this way, you can use the `startFrame` parameter. This parameter defines a specific frame from which playback should start. The feature is supported by all playback modes. So, to start a movie from the 70th frame, you would use an URL similar to this one: `http://mydomain.com/path/movie.html?startingPlaybackMode=0&startFrame=70`

Restricting third-party use of Flash exports

If you put your Flash movies into webpages hosted on the internet, it is possible for third parties to seamlessly embed your Flash movies in their webpages without your consent.

You may want to prevent this, so the Secure Domains and Secure Code settings can be used to restrict how the exported Flash file can be played back from third party domains, webpages and other Flash files. The controls are found on the More tab in the Flash Export Options dialog.

The SecureDomains List

The Secure Domains list determines which domains (in addition to the same domain as the SWF file itself) can host a Flash movie that embeds your exported movie. It does not affect how HTML files can display the movie.

If the secure domains list is empty, then your export can only be loaded and played by SWFs in the same domain.

The SecureCode

The Secure Code further restricts how your Flash exports can be replayed by third party SWF and HTML files, by requiring a parameter to be passed to the movie object before playback.

For example, if you export a movie with the Secure Code set to "123", you will need to do one of two things to enable playback:

- When playing the movie from another SWF file, you need actionscript of the form:

```
exportedmovie.V erifySecurityCode("123")
```

```
exportedmovie.play()
```

- When embedding the movie in HTML, you should pass the secure code as a parameter called "specialcode" like this:

```
<object ...>
```

```
<param name="FLASHVARS" value="specialcode=123">
```

```
...
```

```
</object>
```

or

```
<embed flashvars="specialcode=123" ... />
```

Flash Player Security Warnings

When you open a Flash export on your local hard drive to review it, and use a function in the movie that opens a webpage (like a Button with an Open URL action, or the menu items under the BB FlashBack logo button in the playback controls) you may see an "Adobe Flash Player Security" warning message.

Flash regards an SWF that is on a local hard drive, trying to access a remote webpage, as a security risk and shows this message.

When the SWF is on a web server, there will be no security warning. So this problem only exists when the Flash export is being previewed from your local hard drive.

To workaroud the warning you can add the folder that the SWF is being run from to a list of 'trusted' folders. Do this by right clicking the embedded Flash Player, selecting 'Global Settings' and then selecting to change Global Security Settings. Add the folder to the 'Always trust files in these locations' list.

Exporting to Quicktime (H264)

BB FlashBack can export your movies to Apple QuickTime format. This format is playable on all Apple Macs and PCs that have the QuickTime player installed (this is many PCs, but those in corporate environments are more likely not to have the QuickTime player installed).

The H264 encoding used in QuickTime exports makes it particularly well suited for streaming over the internet, but if you are delivering movies via another media on intend them to be completely downloaded before playing, QuickTime is still capable of excellent results.

Note: exporting to QuickTime requires that you have QuickTime 7 or newer installed.

Technical Note: QuickTime files exported by BB FlashBack use H264 video encoding and the MP4 container format.

How to export to QuickTime format:

1. On the Player main menu, select the Export to QuickTime item on the File menu.

Or

Click the Export button on the File toolbar and select QuickTime format.

2. Set the export options. See below for more details.
3. Give the export file a name and click Save to create the export file.

Setting QuickTime Video Quality and File Size

There are a number of settings you can use to adjust the video quality. Better video quality generally means larger file size.

- **Frame Rate** - A higher frame rate means smoother motion but larger file sizes. Set the Frame Rate on the Frame Rate tab of the QuickTime Export Options window.
- **Key Frame Rate** - More key frames usually mean better quality, but also mean larger file sizes. Set the Key Frame Rate on the Frame Rate tab of the QuickTime Export Options window.
- **Quality** - Set a higher value for higher quality video with less 'artefacts', and larger file sizes. Set the Quality on the Video Quality tab of the QuickTime Export Options window.
- **Single / Multi Pass** Using multi pass encoding will give higher quality results, but will take longer. Select single or multi pass encoding on the Video Quality tab of the QuickTime Export Options window.
- **Data Rate** - A higher data rate (or bitrate) generally means better quality but larger files. The data rate needs to take into account how the movie will be viewed - if the movie will be streamed over the internet, the data rate should be lower than if it will be played from a CD or hard drive. Finding the best data rate for your movie will take some experimentation, so you may want to leave it on the 'automatic' setting and leave the system to pick a rate based on the dimensions of the movie and the quality setting. Set the Data Rate on the Video Quality tab of the QuickTime Export Options window.

Displaying a QuickTime movie in a web page

QuickTime movies can be embedded and displayed in web pages. You will need to copy the exported movie file to a web server and edit the HTML in the web page to reference that file.

A quick tutorial:

http://www.oreillynet.com/pub/a/javascript/excerpt/learnwebdesign_chap22/

Full details on the parameters accepted by the QuickTime movie player object, and things you should know about displaying movies correctly in Internet Explorer.

<http://www.apple.com/quicktime/tutorials/embed.html>

Exporting to Windows Media Video (WMV)

BB FlashBack can export to the Windows Media Video (WMV) format. This format can produce high quality, highly compressed video files that play back on the large majority of Windows PCs. WMV files can only be played on Macs that have installed third party video player software.

Note: the export to WMV function requires that Windows Media Player v9 (or newer) is installed.

How to export to WMV format

1. On the Player main menu, select the *Export to WMV* item on the *File* menu.

Or

Click the *Export* button on the *File* toolbar and select WMV format.

2. Set the export options. See below for more details.
3. Give the WMV file a name and click *Save* to create the export file

WMV Export Options

General Tab

- Export Frames - If you've selected a range of frames, BB FlashBack defaults to exporting just those frames. Otherwise it exports to exporting the entire movie.
- Scaling - Select a value less than 100% to reduce the movie dimensions.

Video Tab

- Frame rate - The higher the frame rate the smoother the movie will look. However, a higher frame rate means that the movie file size will be larger.

Video Quality Tab

- Codec - You should normally select "Windows Media Video 9". The "V8" and "V7" codecs give better compatibility with older PCs, but the vast majority of PCs can play back the version 9 codec now. See WMV compatibility with older PCs[176] if you encounter problems with playback on PCs with older versions of Windows Media Player. The Windows Media Video 9 Screen codec was developed by Microsoft specifically for the purpose of encoding screen capture movies and will usually give the smallest file size. However, the quality will be lower than that seen with Windows Media Video 9.
- Quality - This is a number from 0-100 which determines the quality of the final video output. A higher value means higher quality but increased file size.
- Passes - Selecting two passes will generally result in higher quality but takes longer to export.
- Variable bit rate - You may want to uncheck this box and encode at constant bit rate if you are exporting WMV files intended to be streamed over the internet or are targeting older PCs and devices. Usually a variable bit rate will result in higher quality.

Bitrate - The bitrate determines the quality of the movie: the higher the bitrate the better the quality. It can be useful in controlling the export of files intended to be streamed over the internet.

Note: If your export has 'choppy' playback, or you see the video 'sticking' and not playing smoothly, and you are exporting with variable bitrate unchecked (i.e. using constant bitrate), try increasing the bitrate, decreasing the quality, or both

Audio Tab

- **Codec** - As for the video options, Windows Media Audio series 9 codecs should give the best results. The older codecs are provided in case you encounter problems when playing back the movie on PCs with older versions of Windows Media Player. See WMV compatibility with older PCs[176] for more details.
- **Format** - The sound 'format' is a combination of the sampling rate and whether it is in mono or stereo. The higher the sampling rate the better the quality but the larger the exported movie file. Selecting mono instead of stereo will decrease the movie size but only include one channel of sound instead of two.
- **Passes** - As with the video settings, 2 passes generally results in better quality but takes longer to export.
- **Variable bit rate** - As for the video settings: using variable bit rate will result in higher quality for most purposes, but is less compatible with older media players than constant bit rate encoding.
- **Bitrate/Quality** - A higher value results in better quality but a larger exported movie file.

More Tab

Add 'created by unregistered copy' message - Select this option to add a bitmap to the top right corner of the movie that states that the movie was exported by an unregistered copy of BB FlashBack.

WMV compatibility with older PCs

Video and audio encoded with Windows Media series 9 codecs should play back on most Windows PCs. Certain older PCs might encounter problems, depending on their version of Windows Media Player.

By default, Windows 2000 is installed with Windows Media Player 6.4. Windows ME is installed with version 7 and Windows XP is installed with version 8

Codec	Behavior
Windows Media Video 9	Plays in Windows Media Player 6.4 and later. However, the codec is not installed by default with this version of the player - it will try to automatically find and download it via the internet.
Windows Media Video 9 Screen	Plays in Windows Media Player 7 and later. Does not play in Windows Media Player 6.4. Codec downloads automatically in Windows Media Player 7 and later. Windows Media Player 6.4 cannot find the codec.
Windows Media Audio 9	Constant bit rate: Plays in Windows Media Player 6.4 and later. Variable bit rate: Plays in Windows Media Player 7 and later. Errors or silence in Windows Media Player 6.4.
Windows Media Audio 9 Professional	Plays in Windows Media Player 7 and later. Codec downloads automatically in Windows Media Player 7 and later. Windows Media Player 6.4 cannot find the codec.

Exporting to AVI format

The AVI file format is commonly used to display movies and animation. However, files exported to AVI format will often be larger than the same movie exported to Flash, QuickTime, EXE or WMV format.

Codecs

When exporting a movie to AVI format, you will need to select a codec - the software used to compress and play back the AVI file.

The codec used to export the AVI file has a large impact on its file size and image quality. Because choosing the best codec can require some technical knowledge as well as some testing, exporting to a Flash, QuickTime, WMV or EXE file may be a simpler option.

For more information on codecs and recommendations on how to select one, see [About AVI Codecs](#).

The time taken to export and the eventual file size is largely dependent on four things:

- The length and complexity of the movie.
- The codec used.
- The sound format and compression used (if the movie contains sound).
- The frame rate of the movie - the higher the frame rate, the smoother the movie but the larger the exported file.

How to export a movie to AVI format

1. On the Player main menu, select *File* and *Export to AVI*.

or

On the File toolbar, click the Export button and select AVI format.

2. Select a codec to use for the compression. See [About AVI Codecs](#) for more information.
3. If required, change the dimensions of the movie that you want to export. The movie will be shrunk or expanded to this size to create an AVI movie file with this width and height.
4. Select the frame rate for the export file. The higher the frame rate, the smoother the playback but the larger the exported file. BB FlashBack gives you the option of selecting full frame rate, which gives the smoothest playback and the largest exported file, or 1/2 and 1/4 frame rate which reduce the frame rate to give a smaller, but less smooth, AVI file.
5. If required, set the *Scaling* values to reduce the movie dimensions.
6. If required, change the sound export options. See [Sound export options](#) for details.
7. Click *Export*.
8. Provide a file name for the new AVI movie file and click *Save* to save the movie to that name.

About AVI codecs

A codec is software that is used to generate and play back the AVI movie file. When exporting a BB FlashBack movie file to AVI format, you need to select a codec.

The file size and quality of the exported AVI file is very dependent on the codec used to encode it. If you are getting poor results from your AVI exports, this is probably due to the codec you are using.

The complication of selecting a codec often means that other formats like Flash, Windows Media Video (Std and Pro editions only) and QuickTime (Std and Pro editions only) are a better choice for sharing movies

Finding a good codec

The codecs that are installed with Windows are not the best for getting a good balance of file size and image quality. A free codec that gives much better results is XVID. You can download it from <http://www.xvid.org/Downloads.15.0.html>. Install it on your PC and select it when exporting a BB FlashBack movie.

You should also get good results from the DivX codec (www.divx.com [<http://www.divx.com>])

However, you should be aware that PCs may need the codec installed to play back your export in Windows Media Player.

Windows default codecs

Windows comes with a small number of codecs installed by default: Intel, Full frames, Cinepak and Microsoft Video 1. If you choose one of these you can be fairly sure that the AVI will play back correctly on most Windows PCs.

Intel YUV and Full frames will produce high quality but very large files. Of Microsoft Video 1 and Cinepak, Video 1 tends to give higher but much larger files than Cinepak.

Exporting to MPEG4

MPEG4 format is particularly useful for delivering video exports to devices produced by Apple. Exports in this format need no further conversion to be played back by iPad, iPhone or video capable iPods.

MPEG4 format is not very widely supported on Windows PCs, since Windows Media Player - the default video player on most PCs - does not support MPEG4 playback by default. It requires the installation of 3rd party codecs.

Technical Note: BB FlashBack 'MPEG4' exports use MPEG4-ASP (simple profile, level 1) encoding for video and AAC for audio, in an MP4 container

Optimizing the Export for an Apple Device

BB FlashBack allows you to optimize the dimensions of the export for an Apple device (iPad, iPhone, iPod). You can select a category of device in the 'Optimize for device' setting on the MPEG4 export options window, and dimensions will be set accordingly.

If you export larger or smaller than the recommended dimensions, the video file will still play back ok on the Apple device but it will be scaled to the display size. There is usually nothing to be gained by exporting larger than the display size, but the file size will be larger. Exporting at dimensions much smaller than the display size can result in reduced quality. Using the 'Optimize for device' setting means that you will not be creating unnecessarily large or reduced quality export files

How to export a movie to MPEG4 format

1. On the Player main menu, select the *Export to MPEG4* item on the *File* menu.

Or

Click the Export button on the File toolbar and select MPEG4 format

2. On the dialog that appears, set options for video and audio quality
3. Click *OK* to save the movie to an .mp4 file.

Exporting to Standalone EXE

BB FlashBack can export your movie to an executable file that runs under most versions of Microsoft Windows. To view it, all a user need do is run the file from Windows Explorer, and the movie will open and play automatically.

The user has access to playback controls similar to those in BB FlashBack player and Flash exports, to allow them to jump to any point in the movie, pause and restart playback.

How to export a movie to standalone EXE

1. On the Player main menu, select the Export to Standalone exe item on the File menu.

Or

Click the Export button on the File toolbar and select Standalone EXE format

2. On the dialog that appears, set options for:
 - i. The initial size of the movie player.
 - ii. The toolbar visibility. The toolbar is the set of controls that lets the user stop, pause, continue playback and jump to any point in the movie. You may want to hide this. However, the user can still see the toolbar by right clicking on the movie and selecting 'Show Toolbar'.
 - iii. The movie menu visibility. Similar to the toolbar, the movie menu lets the user control playback of the movie.
 - iv. Cache settings. See the 'cache settings' section below.
 - v. The autoscroll function. The autoscroll function ensures that the mouse cursor is always visible, even if the movie is played back in a window smaller than the movie size.
3. Click OK and provide a file name for the movie to be exported to

The saved EXE can be zipped and sent to users that do not have an installation of BB FlashBack.

Converting exported EXE to an FBR file

Because EXE exports actually contain the FBR file they are exported from, the FBR can be extracted from the EXE. Use the 'Extract FBR from exported EXE' function in the Tools menu in BB FlashBack Player.

Cache Settings

When a user runs the exported EXE and tries to jump to any point in the movie, there is often a small delay while the movie player 'winds forward' to that point and draws the frame. Changing the cache setting can reduce this delay.

Increase the cache size to enable the movie player to jump to random points in the movie more quickly. The drawback to increasing the cache size is that a larger cache uses more memory on the user's PC.

Only increase the cache size from the default of 'minimum' if you believe that users are likely to move around the movie by clicking on the 'timeline' frequently and the movie is quite large (more than 10 minutes).

Select a cache size option in the 'cache' tab of the EXE export dialog

Exporting to MS PowerPoint

BB FlashBack can export your movie to MS PowerPoint format. The generated PPT file will automatically play back the movie when opened.

Note: You will only be able to export to PowerPoint format if you have Office 2000 (or newer) including PowerPoint installed on your PC

How to export to PowerPoint format:

1. On the Player main menu, select the *Export to PowerPoint* item on the *File* menu.

Or

On the *File* toolbar, click the *Export* button then select PowerPoint format

2. If required, change the export options from the default settings. These are the same as the settings used in Flash export, so for more help see Flash export options [162].
3. Click Export
4. Provide a file name for the PPT file and click *Save* to save the movie to that name.

Exporting to GIF

BB FlashBack can export to GIF format. A GIF file is very easy to embed in a webpage but is intended to only show short, small animations at a low frame rate.

It is difficult to give definite limits on frame rate, dimensions etc - they can vary from browser to browser - but you should be careful to avoid poor performance and large file sizes when exporting to GIF format.

How to export to GIF format:

1. On the Player main menu, select the *Export to GIF* item on the *File* menu.

Or

On the *File* toolbar, click the *Export* button then select GIF format

2. On the dialog that appears, set options for video and audio quality.
3. **Note:** to set the GIF to loop playback, use the "Loop playback" setting on the General tab.
4. Click OK to save the movie to a .GIF file.

Sound export options

If the movie you are exporting contains sound, this will also be included in the exported movie file. These audio export options determine the size of the exported file and its sound quality:

- **Format** - The sound 'format' is a combination of the sampling rate and whether it is in mono or stereo. The higher the sampling rate the better the quality but the larger the exported movie file. Selecting mono instead of stereo will decrease the movie size but only include one channel of sound instead of two.

- MP3 compression - This option greatly decreases the size of movies exported with sound. It should only be unchecked if you are experiencing problems with BB FlashBack while exporting movies. The MP3 option is not available in WMV exports.

Note: BB FlashBack uses a redistribution of the open-source LAME MP3 codec: www.mp3dev.org [<http://www.mp3dev.org>]

Batch Exports

BB FlashBack includes a batch export tool that enables you to export a number of files in one go.

To run it, select *Batch Export* Utility from the File menu in BB FlashBack Player.

The batch export tool can also be used to convert FlashBack (FBR) movies from old formats to the newest format via the *Convert to new FBR format* function. This process would normally be performed when the movie was opened in BB FlashBack Player

How to export movies using the batch export tool


1. Add the FBR movies you want to export to the Movies to Export list. Do this by clicking the Add button and selecting the files you require. You can remove files from the export list by selecting them and clicking the Remove button.
2. Select a destination folder. The exported files will be created in here.
3. Select the export format required.
4. Set the export options as you normally would in BB FlashBack. The options you choose will be applied to all the files being exported.
5. Click 'Export' and the process will start. You can cancel the file currently being exported by clicking the *Cancel Current* button, or cancel the entire process by clicking *Cancel All*. The *Status* list at the bottom of the export tool window shows whether each file was successfully exported.

Uploading Movies

BB FlashBack can upload your movies to some popular video hosting sites, enabling you to share movies just by sending a web address. It uploads to YouTube [http://www.youtube.com], Blip.tv [http://blip.tv], Viddler [http://viddler.com] and Revver [http://revver.com]. You need to create an account at the web site before uploading to it

How to Upload a Movie

1. Ensure you have an account for the site you are uploading to.
2. Click the Upload button on the toolbar



By default it uploads to YouTube. Select a different upload profile by clicking on the small arrow at the right of the button. Whatever you select becomes the default for next time.

3. Enter your login details. BB FlashBack needs these to upload the movie to your account. It'll remember them for next time.
4. Enter some information about your movie
 - i. The title and description you enter here will be seen by users that view your movie on the web site.
 - ii. 'Tags' are used to help searching. Give your movie tags relevant to its content.
 - iii. Some sites allow you to make the movie 'private', which means it will only be visible to users you specify.

When BB FlashBack has finished uploading the movie, it'll give you a web address (URL). Open that to see the movie on the video hosting site

Note: some sites can take minutes to process the video. During that time, if you open the URL, you may see a page saying the video is unavailable

Note: movies displayed on video hosting sites can't have interactive elements like 'click to continue' textboxes and buttons. If you want users to see those, you need to export to Flash (SWF) and upload the exported files to your webserver. See Displaying a Flash export on a webpage [168] for more help.

Uploading to FTP and FileCopy

In addition to uploading to public video sharing sites, BB FlashBack also enables you to upload movies to FTP servers and to a location on your PC or LAN.

Uploading to an FTP server

On the Upload button in the Player taskbar, select Upload to FTP. The options on the FTP server details window:

- Server address.g. "ftp.mycompany.com"
- Login name and Password - Your authentication details for the FTP server.
- Home folder - This is the folder on the FTP server that the file will be uploaded to, relative to the default folder for your account.
- Download URL Base - Some FTP servers will have a public download address for a file that is different from the server name and folder name you upload to. In order to have BB FlashBack show a correct download address to the user when the upload completes, you can use the 'Download URL Base' setting. The Download URL Base is the root of the public download address of the file. Say your FTP server has a public download folder set up so that the download address of your file is ftp://myserver.com/public/<filename>. You would enter "ftp://myserver.com/public/" as the Download URL Base. When upload completes, BB FlashBack will add the name of the uploaded file and present the download address as "ftp://myserver.com/public/myfilename.file"

Uploading using the 'FileCopy' profile

The FileCopy profile enables you to copy the FBR movie file, or an export from the file, to a location on your local network. When using the FileCopy upload profile, you need only specify the folder to copy files to. This can be a UNC name or it can contain a drive letter.

Creating upload profiles

BB FlashBack comes with 6 upload profiles by default: YouTube, Blip.tv, Viddler, Revver, FileCopy and FTP. An upload profile describes to BB FlashBack how it should upload movies to a server - the authentication needed (if any), the file format required, the address of the server and how the server wants files to be delivered to it.

You can create your own upload profiles, so you (or other users) can quickly upload movies to web servers, FTP servers or local file servers. BB FlashBack can have an unlimited number of profiles, so you can create profiles for a number of different FTP and local file servers.

You decide what information is editable by the user on upload. You can fix login details, video formats and server addresses, or allow them to be changed when uploading.

How to create an upload profile

1. In BB FlashBack Player, select the Manage Upload Profiles item in the File menu. The item is also in the dropdown menu from the Upload button on the toolbar
2. On the Manage Upload Profiles window, click the Add button
3. **Set the server type and profile name.** You need to tell BB FlashBack what type of server it is uploading to, so it can authenticate and transfer the file successfully. The profile name is displayed in the File->Upload menu, the dropdown menu for the Upload button and on the Upload button
4. **Select available video formats.** BB FlashBack can upload the movie in one of a number of video file formats. On this window, you can select which formats are available to be selected when uploading. Some server types may require files only of a certain format - you cannot upload FBR files to YouTube for example, only WMV, QuickTime, FLV or AVI. If only one video format is selected, the user sees no choice when uploading - the format is selected automatically. If more than one format is selected, the user has to choose the format to upload. If the "Allow user to change video format settings" box is checked, the user sees a window on which they can change video and audio quality settings when uploading. If "Allow user to change video format settings" is unchecked, and only one format is selected, the user sees no choices relating to video file formats when uploading - they give their login details, movie information and BB FlashBack immediately starts the upload
5. **Enter Login and/or Server Details.** Depending on the type of server, you may need to enter server addresses and/or login details. You may select not to enter login details at that time and leave the user to enter their account details when uploading. You can select to have these details editable by the user when uploading

Working with Sound

Adding and Recording Sound into a Movie

BB FlashBack Player enables you to add sound files to a movie, or record commentary or PC sounds into the movie.

When you add a sound file or record new sound, this new sound appears as a new clip in a new track. For more on clips and tracks, see Clips and Tracks [190].

How to add a sound file to a movie

1. Select the frame in the movie at which you want to add the sound.
2. Click the Add button.
3. Select a sound file and click OK. The sound will be added as a new clip in a new track, at the selected frame.

Recording Sound into the movie

BB FlashBack will let you record sound from a microphone (if one is attached) or the sounds you hear from the PC speaker.

1. Select the frame in the movie at which you want to add the recording
2. Click the Sound Record button:
3. You will need to select the recording source - typically either a microphone or the 'PC sounds' you hear through the PC speakers. See Selecting the Recording Source [186] below for more details.
4. Click 'Record'.
5. BB FlashBack will start playback of the movie and record sound from the frame you selected earlier.
6. Press the Stop button on the toolbar to stop recording and playback. The sound will be added as a new clip in a new track, at the selected frame

Selecting the Recording Source

On the Sound Record window, you select the sound source and format to be used by BB FlashBack Player when recording.

Selecting a sound device

Choose a device from the Sound Device drop-down list. Your PC will typically have a "default" sound device and one for each sound card or other sound playback or recording device attached to your PC. Select the device you want to record sound from.

Selecting a sound source

There are three options to choose from:

- **Microphone Select** – Select this to record a commentary from an attached microphone. Use the Level slider and volume indicator on the right of the window to ensure that your microphone is connected and picking up sound correctly. If BB FlashBack does not detect a suitable microphone source attached to your selected sound device, this option will not be enabled.
- **PC Sounds** -Select this option to record what you hear in your PC speakers. A typical sound device (e.g. a sound card) will have a number of 'sources' available for recording. Click the Select Sources button to see the sources that play through your PC speakers. You can select which sources to record and adjust their relative volumes with the mini-sliders. Use the 'level' meters to the right of the Window to make sure BB FlashBack can 'hear' the sound ok for recording.
- **Other Sounds**- Use this to select a sound source that usually does not play back through your PC speakers.

Selecting a sound format

Selecting different sound formats will vary the quality of the recording and the amount of space it occupies in the movie file. You need to select:

- **Sampling rate in Khz** - The higher the rate the better the sound quality but the more file space the sound track occupies.
- **Stereo / Mono** - Stereo will give better sound quality than mono, but also produce larger movie files.

MP3 compression -This option should always be selected unless you are experiencing problems or crashes during recording or export. Deselecting this option may greatly increase the movie file size.

BB FlashBack uses a redistribution of the LAME MP3 codec: www.mp3dev.org [<http://www.mp3dev.org>].

The Sound Options Window

Use this window to :

- Set the sound output device to be used on playback.
- Set options that determine how editing and exporting affects MP3 sounds.

The Playback Tab

This sets the sound device used during movie playback.

The Editing and Exporting Tab

The controls on this tab set two things:

- The 'common' MP3 compression level. When uncompressed sounds are added to a movie, they may need to be converted to MP3. This 'common' compression level is used to compress the sounds.
- Whether MP3 affected by frame editing operations are recompressed. For example, if frames are deleted that lie in the middle of an MP3 sound, the sound may (optionally) also have a section deleted from it. If the sound is not recompressed, there may be a 'click' sound on playback. Setting this option may increase processing time for edit operations that affect sounds.

Sound Synchronisation Problems

Some users may experience problems in audio-video synchronisation. Here are some tips on solving these.

Note that sound sync problems are very hardware dependant - you may find no problems at all if you record on a different PC.

Fixing sync problems in Recorder

Go to the Sound tab of the Recorder Options window, and click the Test Sound Sync button. BB FlashBack will test your sound hardware and, if it can, make adjustments that correct sync problems in subsequent recordings.

Fixing sync problems in existing recordings

If the fix above does not work, or you have existing recordings with sync problems, this process may correct problems.

If the sound is 'ahead' of the video, and reaches the end before the video, you can use the Resynchronise function in BB FlashBack Player to make sound and video end at the same point, correcting the sync.


1. Find the point in the audio at which it 'ends' - this will be before the end of the movie.
2. Select the sound from that point to the end of the movie.
3. Delete the sound, but make sure you do not also delete the movie frames. Only the sound should be selected and drawn in red:
4. Right click on the track header and select Resynchronise. Select to resynchronise to the duration of the movie.


This will resample the sound track to make it the same length as the video, probably correcting sync problems in the process

Changing the Volume of a Track or Clip

To change the volume of a Track or Clip, select it and then use the Volume control on the toolbar.

Select the Track or Clip by clicking its drag handle. Then use the Volume control in the toolbar to increase or decrease the volume.





Removing Noise

BB FlashBack can remove background noise, such as hiss or mains hum, from a sound track.

How to remove noise

1. Select a sound clip or track.
2. Select 'Remove Noise' from the Sound menu or the right click menu for the clip or track.
3. Set the noise removal parameters. The higher the 'Strength' setting, the more noise is removed, but higher values will adversely affect sound quality - you will need to find the right balance between noise removal and sound quality.

The 'remove musical artefacts' setting removes distortion added by the noise removal process. You would normally want this set on, but turning it off can improve quality in some situations

Fading Sounds In or Out

BB FlashBack can fade a sound clip in and out.

How to fade a clip in or out

1. Select the sound clip you want to fade.
2. Select 'Fade clip in/out' from the Sound menu or the right click menu for that clip.

Set the duration of the fade in and out

Volume Level Processing

BB FlashBack can process audio to reduce the problems caused by having widely varying volume levels within a movie.

There are two functions:

- **Compression** - This equalizes volume within a clip, reducing the difference between loud and quiet sounds. It boosts the level of quiet sounds and reduces the level of loud sounds.
- **Normalization** - The adjusts the volume of loud sounds in a number of clips, to give them all the same 'loudness' - the volume of the loudest sound in the clip. It is best used when you have a number of clips with differing volumes.

To apply compression to a clip

1. Select the clip.
2. Select Volume Level Processing -> Even out the Volume Within a Clip on the Sound menu or the right click menu of the clip.
3. Set the strength of the compression.

To apply normalization to a number of clips

1. Select more than one clip by holding the Shift key and clicking the clip handles.
2. Select Volume Level Processing -> Make Multiple Clips Have the Same Loudness on the Sound menu or the right click menu of the clip.


Set normalization to either use the mean volume of the clips or a custom level.

Editing Sound

BB FlashBack works with sound as clips and tracks .

- A clip is a piece of sound that you can move and adjust its volume, independent of all other sounds .
- A number of sound clips together form a track. You could have a track called 'commentary' for example, which contains a number of different commentary sound clips. BB FlashBack shows clips and tracks below the framebar. Each clip is shown as a blue sound "waveform" image, with drag handles.

In the image below, there are 2 tracks: "Commentary" and "Sound Effects". The Sound Effects track contains 2 clips.



When you add a sound file or record a new commentary, the new sound is added as a new clip in a new track.

If you recorded sound with your movie, this sound will appear as a single clip in a track called "main track". The clip will have the same length as the movie.

Note: stereo tracks are shown as one waveform, rather than two images for the two separate channels. The track plays back in stereo, but for the purposes of editing and visualisation, it is shown as one image, and edits apply to both left and right channels.

Moving a clip

At the start and end of each clip are drag handles. Move the start point of a clip in the movie by clicking either handle and dragging to the left or right. This enables you to position sound effects or sections of speech exactly in sync with the video.

Selecting Sound

Select part of a clip by clicking in the clip and dragging to mark an area in red




Select the entire clip by clicking its handle.



Select more than one clip by holding down shift while clicking clip handles. Only adjacent clips can be selected at once.

Select a track by clicking its header. The header will turn red when selected.



BB FlashBack allows you to select the same time period in a number of sound tracks and the movie frames, so you can perform operations on all of them at once.

Changing the volume of sounds

How to change the volume of a part of a clip

1. Click and drag to select part of a clip.
2. Use the volume adjustment control in the toolbar, or right click the clip and select Volume Up or Volume Down from the menu.

Note: BB FlashBack will make your selection into a new clip and change its volume. This means you can easily make further changes to that same selection later.

How to change the volume of an entire clip

1. Click the handle of a clip to select it - the clip will be drawn with a red background.
2. Use the volume adjustment control in the toolbar : or Right click the clip and select Volume Up or Volume Down from the menu.

How to change the volume of an entire track

Right click the track name, and select the Volume Up or Volume Down items.

Muting Sounds

Mute and unmute sound with the Mute toggle button. Muted clips are shown in grey

How to mute part of a clip

1. Click and drag to select part of a clip.
2. Right click the clip and select Mute from its menu.

Note: BB FlashBack will make your selection into a new clip and mute that. This means you can easily unmute that same selection later

How to mute or unmute a clip

1. Click the handle of a clip to select it - the clip will be drawn with a red background.
2. Click the Mute button in the toolbar to mute or unmute it. or Right click the clip and select Mute from its menu.

How to mute or unmute an entire track

Right click the track name, and select the Mute item from its menu.

Merging and Splitting Clips and Tracks


BB FlashBack allows you to select a number of clips and tracks, and merge them together into one.

A single clip can be split into two or three clips, allowing you to position and change the volume of each piece of sound separately

Merging Clips

Select more than one clip by holding down the Shift key and clicking on their handles. Only adjacent clips can be selected.

The selected clips will be shown in red



Merge the clips by clicking the Merge Clip button in the toolbar or selecting Merge Clips from the Sound menu



Merging Tracks

Merge tracks to move all their clips into one track.

How to merge tracks

1. Select a track by right clicking the track 'header' on the left of the Player. The header will turn red to indicate selection.
2. Select all the tracks you want to merge.
3. Right click the header of one of the selected tracks and click 'Merge Tracks' from its menu, or click the Merge Tracks button on the toolbar.

Note: You can only merge tracks when the clips would not overlap when the tracks are combined into one.

Splitting a Clip

BB FlashBack lets you split clips into multiple clips, so you can position and change the volume of each piece of sound separately.

How to split a clip into two

1. Select the point at which you want to split the clip.
2. Click the Split Clip toolbar button , or select the Split Clip item from the Sound menu.

How to split a clip into three, with the selection as the centre clip

1. Select a section of sound.
2. Click the Split Clip toolbar button or select the Split Clip item from the Sound menu. The selected section becomes a clip.



Sound Editing Operations

BB FlashBack allows you to copy and cut sound from a clip, then paste it into another clip or a new track.

How to copy and paste sound

Select some sound in a clip, then use either the Copy or Cut buttons in the Sound toolbar, or the Copy and Cut items on the Sound menu.

To paste the sound into an existing track, select a point in the track and click the Paste button in the Sound toolbar, or the Paste item in the Sound menu.

To paste the sound into a new track, make sure you have no selection in a track when you click Paste - a new track will be created to hold the pasted clip.

Note: these functions do not use the normal Windows clipboard - sound is copied to and pasted from a special sound clipboard only available to BB FlashBack.

Inserting Silence

BB FlashBack enables you to insert silence into sound tracks. You can optionally insert blank frames at the same time.

Select a point in the track and use the Insert button on the Edit toolbar or the Insert Frames/Silence item on the Edit menu.

Note: you can set the length of the silence inserted by selecting a period then using the Insert Silence function - the silence length will default to the selection duration.

Note: if frames are selected then frames will also be inserted into the movie. If frames are not selected, no frames will be inserted by the Insert function. You will know if frames are selected because the Framebar header will be shown in red



Cropping the Movie and Sound Tracks

BB FlashBack allows you to crop sound tracks down to a selected period. You can optionally also crop the entire movie down to the selected period.

Select a period of sound and click the Crop button on the Edit toolbar or the Crop item on the Edit menu.

You'll be asked to confirm the operation, then the selected sound tracks will be cropped to the selected section - everything outside the selection will be deleted.

Note: if frames are selected - i.e. if the Framebar header is drawn in red like this -



then frames will also be cropped to the location. The entire movie length will be reduced.


For more on selecting sound and frames. see [More About Selecting Sound and Frames](#).

More About Selecting Sound and Frames

You can make selections in either the framebar or soundtracks by clicking and dragging, or holding the Shift key while clicking the selection start and end points.


Selecting the same frames/period in many tracks

BB FlashBack enables you to make a selection in one sound track or the framebar and make that same period selected in other tracks. Edit operations can act on the same selection in multiple sound tracks and the movie frames.



To toggle the selection state of the frames or sound tracks, click the header on the left.

The same period is selected in all tracks (or the framebar) in the selected state. So if you clicked the "Sound Effects" track header, a period of sound would be selected corresponding to the already selected frames.



So the same period is selected in both the framebar and the sound track.



Using the Lock option to always include a bar/track in selections

If you want to always include or exclude a bar/track from selections, you can use the lock/unlock toggle button to set this.

In the image below, both tracks are 'unlocked'. If I make a selection in one, the same period will not be selected in the other. Click the button to fix the selection state of the track/framebar. It will change to an icon to show that the state is 'locked'

Using BB FlashBack from the Command Line

BB FlashBack is installed with a program FBCmd.exe that enables recording and exporting from the command line.

Usage:

FBCmd.exe [action] [options]

Actions:

/start	Start recording.
/stop	Stop recording.
/save-config	Overwrite FBCmd configuration with current command line options
/export-configs [filePath]	Export configuration files to the [filePath] folder. configuration files are: "FBCmd Recorder.xml" - options for the recording process "FBCmd ExportWMV.xml" - options for export to WMV "FBCmd ExportFlash.xml" - options for export to Flash "FBCmd ExportAVI.xml" - options for export to AVI You can use these XML files with the /recorder-config, /avi-config, /wmv-config and /swf-config options to use custom settings instead of the current BB FlashBack defaults.

Options for use with the /stop action:

/save-fbr [fileName]	Save recorded movie to [fileName]
/save-avi [fileName]	Export recorded movie to AVI
/avi-config [fileName]	Use AVI export configuration file
/save-wmv [fileName]	Export recorded movie to WMV
/wmv-config [fileName]	Use WMV export configuration file
/save-swf [fileName]	Export recorded movie to Flash
/swf-config [fileName]	Use Flash export configuration file

So to start recording, then stop and save to a WMV file, the commands would be:

FBCMD /start

then

FBCMD /stop /save-wmv c:\test.wmv

This will use the default WMV export settings.

To use a different set of settings, you would get settings as required using BB FlashBack Recorder, then export them to an XML file with the "FBCMD /export-configs" command. Then, when stopping and exporting you could specify the WMV config file via the "/wmv-config" option, like this:

FBCMD /stop /save-wmv c:\test.wmv /wmv-config c:\fbcmd exportwmv.xml

Options for use with the /start action:

/recorder-config [fileName]	Use custom recorder config file
-----------------------------	---------------------------------

Support

First, see if your question is answered by the FAQ below. Then read these pages in the Help documentation:

Troubleshooting Sound Recording

Sound Synchronisation Problems

Troubleshooting Video Recording

Contacting Support

1. Go to the Support menu - in the Help menu in Player, and main menu in Recorder.
2. Select the "Support for BB FlashBack Pro" item and use the contact details shown.

Troubleshooting FAQ

When I installed and when I run Recorder, I see a warning about ASUS software

We have discovered that the ASUS 'Enhanced Display Driver' can cause severe system instability when installed on the same PC as 'mirror' display drivers, of which the FlashBack capture driver is one. Because of the severity of these problems, the capture driver is not installed if BB FlashBack (or its installer) detects an installation of the ASUS driver. BB FlashBack will still be able to record, but it will use the GDI record mode, which may provide lower performance than the capture driver. If the ASUS software is de-installed, the capture driver will be automatically installed on the next run of BB FlashBack Recorder.

My system runs extremely slowly when recording

Try changing the record mode or reducing the frame rate, on the Record Mode tab in the Recorder Options window or the Record Mode step of the record wizard. In particular, you may see problems if you use MPEG mode on a non-multi core CPU (e.g. Intel Pentium 4, Celeron, Atom) or to record a large desktop (larger than 1280x1024).

When recording I see an error message referring to the BB Capture Driver

This may be due to a corrupted install of the Capture Driver, which can be reinstalled through a repair program included with BB FlashBack. Please browse to your BB FlashBack installation directory and run the file "FlashbackDriverInstaller.exe". From this program you can select "Uninstall BB Capture Driver" and then "Install BB Capture Driver" to reinstall the driver correctly.

I'm trying to record a DVD or video clip, but it fails or the results are poor

Take a look at the page Troubleshooting video recording.

What affects the file size of my final movie file?

The file size of your FBR movie file is determined more by the content of your movie, rather than its duration in time. A long movie showing only a static desktop is likely to be much smaller in size

than a short movie containing numerous graphics and photos. Material which will boost movie size considerably includes photos, custom Windows wallpaper, website images, animations, scrolling windows and Windows graphics effects.

In BB FlashBack you can switch off graphical wallpaper and Windows graphics effects automatically while recording. These options can be found in the Recorder Options dialog, Graphics tab.

A soundtrack will also raise the final size of your movie. To reduce the size added by a soundtrack you should enable the "MP3 Compression" in the sound recording options (Recorder Options --> Sound tab) and import MP3 rather than WAV files when adding sounds in the Player application.

File sizes vary considerably when exporting to another (non-FBR) format. Flash format is often smaller than AVI, although the codec selected when exporting to AVI is a major factor in determining the file size.

When I replay my movie graphics or text are not displayed correctly or missing altogether

If you are using a computer with more than one graphics card, you should go to the Windows control panel --> display --> settings tab --> advanced - and switch the primary graphics card to your other video card.

If you are recording moving video or animation, you should use MPEG mode, rather than GDI or Capture driver modes.

I cannot hear any sound when replaying my movie

The first thing is to test whether sound is working in general on your computer. Try playing a sound file - if you can't hear the music file play, then your system probably hasn't got sound correctly configured.

If you are using your PC microphone to try and record sound, a good test is to run the standard Windows' Sound Recorder program to try and record and replay a test. If you cannot hear the test, it is likely that your PC is not correctly configured to use the microphone as a sound recording source. You may need to change the sound source or increase its volume.

Do this via the Edit Audio Properties menu item in the Windows Sound Recorder. Select the correct sound device for sound recording and ensure that the volume level is satisfactory by recording and playing back a voice recording.

By default you can find the Windows' Sound Recorder program under Start menu --> Programs --> Accessories --> Entertainment.

If you know that sound is correctly installed on your computer, please go to the BB FlashBack Recorder --> Options --> Sound tab and check that the "enable sound recording" option is switched on (if switched off no sound will be captured when recording a movie).

Take a look at the help topic Recording Sound - this will give instructions on how to record from a microphone or PC speaker sounds.

My licence key is not accepted by the program

Please note that trial keys are case sensitive and include spaces.

For more help with licence key related problems, see Problems with licence keys.

My FBR movie file will not open in the Player

If the file is corrupted there is no automatic way of recovering the file. The best option is to restore from your most recent backup.

I've exported my movie to an AVI file. This plays fine on my PC but not in other computers

When you export to AVI, BB FlashBack prompts you to select a codec from a list of all the codecs installed on your machine. The selected codec needs to be installed on the playing computer in order to view your AVI movie. You should either advise the viewer to either use a movie player like VLC (www.videolan.org) that has built-in compatibility with many codecs, or install the relevant codec. Or you could export using another codec or to a different format.

When I export to any format, I get a 'created by' image in the top right corner. Will this appear when I buy a licence?

No - the 'created by' image only appears in exports made by an unlicensed copy of BB FlashBack.

I've exported my movie to Flash but the SWF file appears distorted or low quality

When exporting to Flash format BB FlashBack creates both a HTML and a SWF file, both of which are required to view your movie. You should open the HTML file in order to see your movie at the correct size and quality.

I record with sound, but when I play back the movie, the sound and video become more and more out of sync

This problem can occur with certain sound hardware. Go to the Advanced tab of the Recorder Options window, and check the Use extra sound synchronisation box.

Reporting Problems

BB FlashBack enables you to report problems in its execution back to Blueberry. It will automatically create a log of recent runs, gather information about your PC configuration and make it easy to add screenshots to the report.

To be able to send a record of its recent execution, BB FlashBack needs to have Logging switched on. By default, Logging is switched off.

How to report a problem to Blueberry

1. Turn on logging

Start BB FlashBack and select the "Enable Logging Autorun" menu item from the Support menu.

- In Player, the Support menu is in the Help menu.
- In Recorder, it is in the main menu.

If you cannot start BB FlashBack, select the item "Enable Logging Autorun" from the Support menu in the BB FlashBack menus under the Windows Start button

2. Reproduce the problem

Restart BB FlashBack (Player or Recorder) and reproduce the problem

3. Start the report

Go to 'Report Problem to Blueberry'. This is in the Help -> Support menu in Player, and the Support menu in Recorder

4. Send the report

Fill in the description (and the email address if you want us to get back to you) and click Send.

You can attach screenshots or files to the report by clicking the Change Attachments button on the Fault Report window.

Checking for Updates to BB FlashBack

BB FlashBack can check to see if a newer version of the application is available. If it finds a newer version than the one you are running, it will give you the option of downloading and installing it. The checking and download requires an Internet connection - if none is active and your Internet settings use dial-up connections, you will be prompted to dial your default connection.

How to check for updates to BB FlashBack

1. Select *Check for updates* on the Player *Help* menu or the Recorder main menu.
2. Follow the instructions on the Automatic update wizard to check for a newer version, and if there is one, download and install it

Automatic check for updates

BB FlashBack can also check for updates in the background, while you are working. If it finds one, it will ask you whether you want to download and install it now.

How to turn on or off automatic updates

1. Select the *Tools -> Player Options* menu item.
2. Check or uncheck the auto-update checkbox

How to turn automatic update checking on and off in Recorder

1. From the Recorder main menu select the *Options* item.
2. Select the *Misc* tab on the options dialog.
3. Check or uncheck the auto-update checkbox.